



# BASh

## Developer Documentation v1.5.9

©1998-2001 Deep Sky Technologies, Inc. All Rights Reserved.  
Published and Distributed Worldwide by Deep Sky Technologies, Inc.

Deep Sky Technologies, Inc.  
P.O. Box 6897  
Vero Beach, FL 32961-6897  
(561) 794-9494



<http://www.deepskytech.com/>

### Software Engineers

James T. Crate  
Robert T. McGoye  
Steven G. Willis

### Manual

Steven G. Willis



# Software License and Limited Warranty

Please read this license carefully before using the software. By using the software, you agree to become bound by the terms of this agreement, which includes the software license and warranty disclaimer (collectively referred to herein as the "agreement"). This agreement constitutes the complete agreement between you and Deep Sky Technologies, Inc. If you do not agree to the terms of this agreement, do not use the software and promptly destroy all copies in your possession, physical and electronically.

**1. Ownership of Software:** The enclosed manual and computer programs ("Software") were developed and are copyrighted by Deep Sky Technologies, Inc. ("DSTi") and are licensed, not sold, to you by DSTi for use under the following terms, and DSTi reserves any rights not expressly granted to you. DSTi retains ownership of all copies of the Software itself. Neither the manual nor the Software may be copied in whole or in part except as explicitly stated below.

**2. License:** DSTi, as Licensor, grants to you, the Licensee, a non-exclusive, non-transferable right to use this Software subject to the terms of the license as described below:

- a. You may make backup copies of the Software for your use provided they bear the DSTi copyright notice.
- b. You may use this Software in an unlimited number of custom or commercial databases or applications created by the original licensee. No additional product license or royalty is required.

**3. Restrictions:** You may not distribute copies of the Software to others (except as an integral part of a database or application within the terms of this License) or electronically transfer the Software from one computer to another over a network. You may distribute copies of the Software as an integral part of a development shell or non-compiled commercial database as long as the DSTi copyright notices and documentation remain intact with the distribution. The Software contains trade secrets and to protect them you may not decompile, reverse engineer, disassemble, or otherwise reduce the Software to a human perceivable form. You

may not modify, adapt, translate, rent, lease, loan or resell for profit the software or any part thereof.

**4. Termination:** This license is effective until terminated. This license will terminate immediately without notice from DSTi if you fail to comply with any of its provisions. Upon termination you must destroy the Software and all copies thereof, and you may terminate this license at any time by doing so.

**5. Update Policy:** DSTi may create, from time to time, updated versions of the Software. At its option, DSTi will make such updates available to the Licensee.

**6. Warranty Disclaimer:** The software is provided "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. DSTi does not warrant, guarantee, or make any representations regarding the use, or the results of the use, of the software or written materials in the terms of correctness, accuracy, reliability, currentness or otherwise. The entire risk as to the results and performance of the software is assumed by the Licensee. If the software or written materials are defective you, and not DSTi or its dealers, distributors, agents, or employees, assume the entire cost of all necessary servicing, repair or correction. No oral or written information or advice given by DSTi, its dealers, distributors, agents, or employees shall create a warranty or in any way increase the scope of this warranty, and you may not rely on such information or advice. This warranty gives you specific legal rights. You may have other rights, which vary from state to state.

**7. Governing Law:** This agreement shall be governed by the laws of the State of Florida.

# Copyrights and Trademarks

All trade names referenced in this document are the trademark or registered trademark of their respective holder.

BASh, TCP Deux, SMTP Deux, POP3 Deux, FTP Client Deux, HTTP Client Deux, and eTrans are copyright Deep Sky Technologies, Inc.

4th Dimension, ACI, ACI US, 4D Compiler, 4D, 4D Server, 4D Client, and 4D Insider are trademarks of 4D, Inc.

4D Pack plugin provided courtesy, and with permission, of 4D, Inc.

Macintosh and MacOS are trademarks of Apple Computer, Inc.

Windows is a trademark of Microsoft Corporation.

Marshmallow Peeps and Just Born are trademarks of Just Born, Inc.

# Table of Contents

Items in **Bold** were just added in the latest release of the BASH component.  
Items in *Italic* have not had their content filled in completely as of yet.  
Items in Underline have had important updates since the last release of the BASH component.

Software License and Limited Warranty

Copyrights and Trademarks

Table of Contents

Preface

Acknowledgements

Features

    System Requirements

    Support

Components

    Installing and Updating BASH

        Managing Installation Conflicts

        Affix BASH Document

        4D Pack Plugin

    Uninstalling BASH

    Updating to BASH v1.5.9

Constants

    URL Schemes

Modules

    ARR Module

        ARR\_Add\_Elements\_to\_End

        ARR\_Add\_Elements\_to\_Top

        ARR\_Clear

        ARR\_Coerce\_from\_Text

        ARR\_Coerce\_to\_Text

        ARR\_Convert\_Longint\_to\_Text

        ARR\_Convert\_Text\_to\_Longint

        ARR\_Convert\_Type\_to\_Longint

        ARR\_Cycle\_Stack

        ARR\_ERROR

**ARR\_Find\_First\_Binary**

**ARR\_Find\_Last\_Same**

        ARR\_Order\_to\_Match

        ARR\_Pack\_to\_Text

        ARR\_Populate\_Text\_Array

        ARR\_Remove\_Elements\_from\_End

        ARR\_Remove\_Elements\_from\_Top

ARR\_Set\_Size  
ARR\_Set\_Sizes

#### BLOB Module

BLOB\_Append\_Text  
BLOB\_BLOB\_to\_Document  
**BLOB\_Change\_Case**  
BLOB\_Clear  
BLOB\_Document\_to\_BLOB  
BLOB\_Find\_Between\_Folding\_x  
BLOB\_Find\_Between\_x  
BLOB\_Find\_Byte  
BLOB\_Find\_Text\_Case  
BLOB\_Find\_Text\_NonCase  
BLOB\_Finds\_Between\_Folding\_x  
BLOB\_Replace\_Byte  
BLOB\_Replace\_Text\_Case  
BLOB\_Replace\_Text\_NonCase  
**BLOB\_XOR\_Bytes**

#### CODEC Module

##### CLE Encoding Scheme

CODEC\_Decode\_Base64\_x  
CODEC\_Decode\_Base64\_z  
CODEC\_Decode\_CLE\_x  
CODEC\_Decode\_Hex\_x  
CODEC\_Decode\_Hex\_z  
CODEC\_Decode\_URL\_x  
CODEC\_Decode\_URL\_z  
CODEC\_Decode\_UUEncode\_File  
CODEC\_Decode\_UUEncode\_x  
CODEC\_Decode\_UUEncode\_z  
CODEC\_Encode\_Base64\_x  
CODEC\_Encode\_Base64\_z  
CODEC\_Encode\_CLE\_x  
CODEC\_Encode\_CRAMMD5\_z  
CODEC\_Encode\_Hex\_x  
CODEC\_Encode\_Hex\_z  
CODEC\_Encode\_KeyedMD5\_z  
CODEC\_Encode\_MD5\_x  
CODEC\_Encode\_MD5\_z  
CODEC\_Encode\_URL\_x  
CODEC\_Encode\_URL\_z  
CODEC\_Encode\_UUEncode\_File  
CODEC\_Encode\_UUEncode\_x

- CODEC\_Encode\_UUEncode\_z
  - CODEC\_ERROR
- CONV Module
  - Hex2 and Hex8 Values
  - Type Values
  - Dotted IP Values
    - CONV\_ASCII\_to\_Hex2
    - CONV\_ASCII\_to\_PrintableText
    - CONV\_Coerce\_from\_Text
    - CONV\_Coerce\_to\_Text
    - CONV\_ERROR
    - CONV\_Hex8\_to\_Longint
    - CONV\_Hex8\_to\_Text
    - CONV\_IP\_to\_Longint
    - CONV\_Longint\_to\_Hex8
    - CONV\_Longint\_to\_IP
    - CONV\_Longint\_to\_Type
    - CONV\_Text\_to\_Hex8
    - CONV\_Text\_to\_Longint
    - CONV\_Text\_to\_Real
    - CONV\_Type\_to\_Longint
- CRYPT Module
  - Tiny Encryption Algorithm (TEA)
    - CRYPT\_Decrypt\_TEA\_x
    - CRYPT\_Decrypt\_TEA\_z
    - CRYPT\_Encrypt\_TEA\_x
    - CRYPT\_Encrypt\_TEA\_z
    - CRYPT\_Get\_TEA\_Keys\_f\_Text
- DATE Module
  - DATE\_Get\_ISO8601\_GMT
  - DATE\_Get\_Month\_f\_ShortName
  - DATE\_Get\_RFC\_GMT
- DSS Module
  - Variable Classifications
    - DSS\_ERROR
    - DSS\_Get\_Variable\_by\_Type
    - DSS\_Get\_Array\_by\_Unary\_Type
    - DSS\_Get\_Unary\_by\_Array\_Type
    - DSS\_Return\_Variable
- DTS Module
  - DTS Values
    - DTS\_Add
    - DTS\_Add\_Normalize



DTS\_Convert\_f\_RFC  
DTS\_Get\_Current  
DTS\_Get\_Date  
DTS\_Get\_Date\_Time  
DTS\_Get\_Day  
DTS\_Get\_Maximum  
DTS\_Get\_Month  
DTS\_Get\_Range  
DTS\_Get\_Time  
DTS\_Get\_Year  
DTS\_Make\_from\_DateTime  
DTS\_Make\_from\_Values  
DTS\_Subtract  
DTS\_Subtract\_Normalize

#### ENV Module

ENV\_ERROR  
ENV\_Get\_4DApplication\_FullPath  
ENV\_Get\_4DXOS\_FolderPath  
ENV\_Get\_4DX\_FolderPath  
ENV\_Get\_Application\_Name  
ENV\_Get\_Application\_Name\_Short  
ENV\_Get\_Application\_Type  
ENV\_Get\_BASh\_HardName\_Long  
ENV\_Get\_BASh\_HardName\_Short  
ENV\_Get\_BASh\_RF\_FullPath  
ENV\_Get\_DataFile\_FolderPath  
ENV\_Get\_DataFile\_FullPath  
ENV\_Get\_DirectorySymbol  
ENV\_Get\_DirectorySymbol\_by\_OS  
ENV\_Get\_Platform  
ENV\_Get\_Structure\_DF\_FullPath  
ENV\_Get\_Structure\_FolderPath  
ENV\_Get\_Structure\_RF\_FileName  
ENV\_Get\_Structure\_RF\_FullPath  
ENV\_q\_Macintosh  
ENV\_q\_Windows  
ENV\_Set\_FlushKey

#### FILE Module

##### Hard File Names

FILE\_Convert\_to\_ResFork\_Windows  
FILE\_Create\_Document  
FILE\_Create\_Folder  
FILE\_Create\_FullPath\_Document

- FILE\_Create\_FullPath\_Folder
- FILE\_ERROR
- FILE\_Find\_FileName\_Hard\_Long
- FILE\_Find\_FileName\_Hard\_Short
- FILE\_FullPath\_to\_FileName
- FILE\_Get\_Document\_List
- FILE\_Get\_Path\_Parent
- FILE\_Get\_Volumes\_Names
- FILE\_qi\_Document\_Exists
- FILE\_qi\_Folder\_Exists
- FILE\_qi\_Volume\_Exists
- INIT Module
  - INIT\_BASH
- NULL Module
  - NULL\_Dereference\_by\_Type
  - NULL\_ERROR
  - NULL\_Get\_DTS
  - NULL\_Get\_Pointer
  - NULL\_Set\_Variables
- NVP Module
  - NVP\_ERROR
  - NVP\_Extract\_Values\_by\_Name\_s
  - NVP\_Extract\_Values\_by\_Name\_x
  - NVP\_Pack\_to\_Text
  - NVP\_Parse\_to\_Arrays
- PROS Module
  - PROS\_Delay\_Current
  - PROS\_Get\_Type
  - PROS\_Get\_UniqueID
- PTEXT Module
  - Parameter Text Values
    - PTEXT\_Set\_Values\_ax
    - PTEXT\_Set\_Values\_az
    - PTEXT\_Set\_Values\_x
    - PTEXT\_Set\_Values\_z
- RES Module
  - 'fMap' Resource*
  - 'HTbl' Resource*
  - 'LoCK' Resource*
  - 'MENV' Resource*
  - 'WAGr' Resource*
  - 'WPGr' Resource*
  - RES\_Close

RES\_Create\_File  
RES\_Delete\_Resource  
RES\_ERROR  
RES\_Get\_Fork\_Size  
RES\_Get\_Resource\_List  
RES\_Get\_TEXT\_Resource  
RES\_Load\_cicn  
*RES\_Load\_fMap*  
RES\_Load\_HTbl  
*RES\_Loadack\_LoCK*  
RES\_Load\_MBAR  
RES\_Load\_MENU  
*RES\_Load\_MENV*  
RES\_Load\_PICT  
RES\_Load\_TMPL  
*RES\_Load\_WAGr*  
*RES\_Load\_WPGr*  
RES\_Make\_TMPL\_f\_Arrays  
RES\_Open  
RES\_Open\_BASh  
RES\_Open\_4DApplication  
RES\_Open\_DateFile  
RES\_Open\_Structure  
*RES\_Parse\_HTbl\_Cells*  
*RES\_Parse\_HTbl\_Rows*  
*RES\_Parse\_HTbl\_Table*  
RES\_Parse\_TMPL  
RES\_Set\_HTbl\_Resource  
RES\_Set\_Resource\_Name  
RES\_Set\_Resource\_Properties  
RES\_Set\_TEXT\_Resource

#### SEM Module

SEM\_Clear\_One  
SEM\_ERROR  
SEM\_Set\_One  
SEM\_Test\_One

#### SERNO Module

SERNO\_Create\_SerialNumber  
SERNO\_Decode\_SerialNumber  
SERNO\_Get\_Beta  
SERNO\_Get\_MajorVersion  
SERNO\_Get\_MinorVersion  
SERNO\_Get\_Month

- SERNO\_Get\_ProductCode
- SERNO\_Get\_Users
- SERNO\_Get\_Year

#### STR Module

- STR\_Clean\_EmailAddress
- STR\_Clean\_EmailUsername
- STR\_Concatenate\_Text
- STR\_Count\_Occurrences\_of\_ASCII
- STR\_Count\_Occurrences\_of\_String
- STR\_Get\_CharPosition\_by\_ASCII
- STR\_Get\_Line\_First
- STR\_Pad\_String
- STR\_Parse\_to\_Array\_by\_ASCII
- STR\_Parse\_to\_Array\_by\_Str
- STR\_Position\_NonAlpha
- STR\_Position\_NonAlphaNumeric
- STR\_Position\_NonNumeric
- STR\_qi\_Match\_Filter\_NonCase
- STR\_Remove\_After\_Last\_by\_ASCII
- STR\_Remove\_Line\_First
- STR\_Remove\_NonAlphaNumeric
- STR\_Remove\_Spaces\_Post
- STR\_Remove\_Spaces\_Pre
- STR\_Remove\_Spaces\_PrePost
- STR\_Replace\_ASCII\_All
- STR\_Wrap\_in\_DoubleQuotes

#### TIME Module

- TIME\_Add\_Normalize
- TIME\_Get\_Hours
- TIME\_Get\_Minutes
- TIME\_Get\_Seconds
- TIME\_Get\_Sum\_Offset

#### TYPE Module

- Unary and Array Classifications
  - TYPE\_Compare\_Dereferenced\_Type
  - TYPE\_Get\_Array\_by\_Unary
  - TYPE\_Get\_Unary\_by\_Array
  - TYPE\_qi\_Array
  - TYPE\_qi\_BLOB

#### URL Module

- Fully Formatted URLs
  - URL\_Extract\_DirectParam
  - URL\_Extract\_Host

- URL\_Extract\_Password
- URL\_Extract\_Path
- URL\_Extract\_Path\_w\_Params
- URL\_Extract\_Port
- URL\_Extract\_Scheme\_i
- URL\_Extract\_Scheme\_x
- URL\_Extract\_SearchParams
- URL\_Extract\_Username
- URL\_Get\_Scheme\_i
- URL\_Get\_Scheme\_x
- URL\_Make\_URL

#### VAR Module

- VAR\_Get\_Variable\_Name
- VAR\_qi\_Null\_Pointer

#### WORD Module

- WORD\_Add\_Unsigned
- WORD\_Clear\_Bits
- WORD\_Get\_Bit\_Range
- WORD\_Rotate\_Left
- WORD\_Set\_Bits

#### Version History

##### **BASh v1.5.9**

BASh v1.5.8

BASh v1.5.7

BASh v1.5.6

BASh v1.5.5

BASh v1.5.4

BASh v1.5.3

BASh v1.5.1

BASh v1.4.7

BASh v1.4.6

BASh v1.4.1

BASh v1.4.0

BASh pre-v1.4.0

#### *BASh Error Codes*

# Preface

The BASH component is distributed solely as “Peepware”. Of course, this is as opposed to distribution as freeware or postcardware.

In case you are not familiar with peepware, it is considered very similar to postcardware. If you find the methods and functionality available within this software to be useful, we ask that you send along your favorite variety of marshmallow peeps to the programming staff at Deep Sky Technologies, Inc.

Just in case, if you have no idea what marshmallow peeps are, please visit <http://www.marshmallowpeeps.com/> and become a fan of the greatest programmer food to have ever existed.

# Acknowledgements

The creation of the BASH component is not directly attributable to any single person. Particular pieces of functionality within the BASH component may be from the direct knowledge and experience of certain developers, but the overall concept and construction of the BASH component has come from all of the developers at Deep Sky Technologies, Inc.

In particular the tireless efforts of Robert T. McGoye have contributed the most to the BASH component. His ability, and patience, to be able to tolerate the swings in the atmosphere at DSTi have proven to be invaluable in the development of the BASH component. Mr. McGoye fill a roll early in expansion of DSTi which proved invaluable to the eventual release of the BASH component.

Later additions and enhancements to the BASH component have resulted from the training of James T. Crate. Mr. Crate's experience in many different programming environments has provided refreshing insights into the overall structure and organization of the core routines at DSTi, the same core routines which are available in the BASH component.

For different particular pieces of functionality within the BASH component, many different individuals provided interesting feedback and techniques which have contributed to the code with the BASH component. These list of these people include, though is not limited to: David Adams, Charles Albrecht, Stewart Buskirk, Tim Crusher, Michael Erickson, Kieth Goebel, Bryan Green, Jerry Hale, Tim Klein, and Tom Lundeen.

Finally, I, Steven G. Willis, might have had something to do with the creation of the BASH component...





# Features

The BASH component consists of many different modules of methods which provide extensive utility services in 4th Dimension applications. The list of modules currently available in the BASH component is:

- ARR - Array sizing, management, and manipulation methods;
- BLOB - BLOB management and manipulation methods;
- CODEC - encoding and decoding support for common formats;
- CONV - conversion methods to handle data and type conversions;
- CRYPT - encryption and decryption routines;
- DATE - provides basic date manipulation routines;
- DSS - Dynamic Stack Space; reusable variable management system;
- DTS - Date-Time Stamps; generation and manipulation methods;
- ENV - environmental information (program, OS, CPU, etc.);
- FILE - path and file name utilities;
- INIT - module and component initialization;
- NULL - Variable clearing and initialization methods;
- NVP - named value pair utilities and management;
- PROS - process information accessors;
- PTEXT - parameter text replacement routines;
- RES - resource management and utility methods;
- SEM - Semaphore management methods;
- SERNO - serial number generation and confirmation methods;
- STR - string manipulation, formatting, and filtering methods;
- TIME - Time manipulation methods;
- TYPE - Variable type comparison methods;
- URL - URL creation and extraction routines;
- VAR - Variable utility methods;
- WORD - manipulators for non-native four-byte values.

Items in **Bold** were just added in the latest release of the BASH component. Items in Underline have had important updates in BASH v1.5.9, the latest release.

# System Requirements

The BASH component is compatible with both Macintosh and Windows installations of 4th Dimension.

Since it is a component, it does require at least version 6.7 of 4th Dimension or above, including 4D Insider v6.7 or above for installation.

Other than the normal hardware and software requirements for your version of 4th Dimension, there are no other minimum requirements for proper use of this software.

# Support

As peepware, there obviously is no guaranteed support which is available for the BASH component.

But, on an “as available” basis, with no implied or expressed warranty for support whatsoever, Deep Sky Technologies, Inc., can be contacted for support for the software in the BASH component.

Contact information, including email address(es), phone number(s), and a Contact Us request form, for Deep Sky Technologies, Inc., can be found on the DSTi web site located at:

<http://www.deepskytech.com/>



# Components

A component groups various 4D objects (tables, project methods, forms, menu bars, variables, etc.) representing one or more additional functions. Developing a 4D component providing electronic mail functionality is one such example. A component is autonomous and must be able to be installed in any 4D structure.

Components are defined, generated, and installed with the help of 4D Insider. The component definition is based on the cross referencing analysis performed by 4D Insider (target objects and source objects).

Unlike libraries and groups, components embed the idea of security of objects that they compose. During the development phase of the component, each object is attributed an access type, "Public", "Protected" or "Private". This attribute determines whether each object will be visible or modifiable in 4th Dimension and in 4D Insider once the component is installed within a 4D database.

## Installing and Updating BASH

Installing BASH or updating an existing version of BASH within a 4D database is performed using 4D Insider. The activity primarily consists of installing the BASH component in a database structure opened with 4D Insider (installing the BASH component in a library is not supported at this time).

4D Insider will manage possible conflict issues within the installation and will inform you as they are detected. Though, with the naming conventions used within the BASH component and the limited number of object names, conflicts should be very rare.

To install or update the BASH component, follow these very simple steps:

**Open the uncompiled structure that you wish to install BASH into using 4D Insider.**

**Choose the "Install/Update..." command in the "Components" menu.**

A standard open file dialog box will appear.

**Select the BASH component file and click on the "Open" button.**

4D Insider parses the BASH component and prepares to integrate it with your open database. 4D Insider will detect if the operation is an installation or an update of the BASH component.

In the event of a new installation, all BASH objects are installed.

In the event of an update, 4D Insider compares the version numbers of both the currently installing BASH component and the already installed BASH component. If the date of the "new" component is older than the already installed component, a dialog box will alert you, allowing you to then "Continue" or "Cancel" the update.

4D Insider replaces old objects with newer objects within the BASH component and adds new objects from the new BASH component. 4D Insider takes into account "public" objects having been modified by you (e.g. "\_ERROR" methods) and will prompt you to either save or replace them. If any other conflicts arise from the installation or update of the BASH component, 4D Insider will prompt you with an appropriate dialog box.

**Save the database in 4D Insider.**

**Place a copy of the Affix BASH document in the 4DX folder.**

The Affix BASH document (entitled **Affix\_BASH**) contains essential data and resources for many of the methods within the BASH component. For many of the methods within the BASH component to function properly, the Affix BASH document must be in the 4DX folder for the current structure.

On Macintosh, the Affix BASH document is entitled **Affix\_BASH** and is located in the Mac4DX directory in the BASH component's archive. The document should be copied into the Mac4DX folder of your current structure. If the BASH component is going to be used in all of your 4D projects, the Affix BASH document can instead be placed within the Mac4DX folder within the 4D folder of your system.

On Windows, the Affix BASH document is actually two documents: **Afx\_BASH.4DX** and **Afx\_BASH.RSR**. These two documents correspond to the data fork and the resource fork of the Affix BASH document used on Macintosh. These documents are located in the Win4DX directory in the BASH component's archive. These documents should be copied into the Win4DX folder of your current structure. If the BASH component is going to be used in all of your 4D projects, the Affix BASH document can instead be placed within the Win4DX folder within the 4D folder of your system.

For client/server installations in cross-platform environments, both the Macintosh and Windows versions of the Affix BASH document should be installed.

**Place a copy of the 4D Pack plugin in the 4DX folder.**

The 4D Pack plugin (entitled **4dp\_v671**) contains essential commands and functionality used within the BASH component. For many of the methods within the BASH component to function properly, the 4D Pack plugin must be in the 4DX folder for the current structure.

On Macintosh, the 4D Pack plugin included with the BASH component download is entitled **4dp\_v671** and is located in the Mac4DX directory in the BASH component's archive. The plugin should be copied into the Mac4DX folder of your current structure. If the BASH component is going to be used in all of your 4D projects, the plugin can instead be placed within the Mac4DX folder within the 4D folder of your system.

On Windows, the 4D Pack plugin included with the BASH component is actually two documents: **4dp\_v671.4dx** and **4dp\_v671.rsr**. These two documents correspond to the data fork and the resource fork of the 4D Pack plugin used on Macintosh. These documents are located in the Win4DX directory in the BASH component's archive. These documents should be copied into the Win4DX folder of your current structure. If the BASH component is going to be used in all of your 4D projects, the 4D Pack plugin documents can instead be placed within the Win4DX folder within the 4D folder of your system.

For client/server installations in cross-platform environments, both the Macintosh and Windows versions of the 4D Pack plugin should be installed.

**Call the method *INIT\_BASH* early in the On Startup database method.**

Beginning with BASH v1.5.4, the modules in the component must now be manually initialized. This is



being done to alleviate minor bugs and limitations in the 4D implementation of component code.

To initialize the BASH component in your code, place a call to the method *INIT\_BASH* early in your **On Startup** database method.

Details about the INIT module and the *INIT\_BASH* method can be found in the module and method documentation, below.

The BASH component is now installed/updated in your database and is listed on the "Components" page of the 4D Explorer.

## Managing Installation Conflicts

On very rare occasions, when the BASH component is installed or updated in your 4D database, several questions and conflicts may arise. In the event of an update, 4D Insider will detect that you have modified one of more "Public" objects in BASH after the initial installation. Or, one or more objects of the same type and of the same name may already exist in your database and in the BASH component.

4D Insider detects and solves these conflicts during installation:

### Modified public objects (updates only)

In this case, 4D Insider alerts you by a dialog box, allowing you to choose an update mode:

Replace the object

Replace all objects

Do not replace the object

Stop installation

## Name conflicts

In this case, 4D Insider stops the BASH's installation process, alerts you through a dialog box and saves the list of objects in conflict. This list is stored as a text file in the 4D database folder.

Naming conflicts between logical objects, such as variables, are managed by 4D Insider, in a manner that allows database compilation and avoids conflicts between BASH and other 4D components.

It may be necessary to rename certain objects in your database or in other components in order to be able to install the BASH.

If any naming conflicts do occur between BASH and other 4D components, please notify Deep Sky Technologies, Inc., immediately.

## Affix BASH Document

The Affix BASH document (entitled **Affix\_BASH** on Macintosh; entitled **Afx\_BASH.4DX** and **Afx\_BASH.RSR** on Windows) contains essential data and resources for many of the methods within the BASH component. For many of the methods within the BASH component to function properly, the Affix BASH document must be in the 4DX folder for the current structure. For distributed and installed versions of your 4D projects, the Affix BASH document must be available in the 4DX folder for the BASH methods to continue to function properly.

**Note:** it is best to consider the Affix BASH document another plug-in within your 4D project. Though there no actual plug-in calls available within the Affix BASH document, it does contain data and resources essential to the operation of the BASH methods. The BASH component has been designed to find the Affix BASH document correctly in all environments (any platform, any 4DX folder, single

user or clients/server, etc.). Since the Affix BASH document is configured similarly to plug-ins, 4D and the BASH component will automatically manage the document for you in all of the possible installations of a 4D project.

## 4D Pack Plugin

The 4D Pack plugin (entitled **4dp\_v671**, included with the BASH component archive) contains essential calls for many of the methods within the BASH component. For many of the methods within the BASH component to function properly, the 4D Pack plugin must be in the 4DX folder for the current structure. For distributed and installed versions of your 4D projects, the 4D Pack plugin must be available in the 4DX folder for the BASH methods to continue to function properly.

The 4D Pack plugin is provided unmodified directly from 4D, Inc., and 4D SA. Copies of the plugin are included with the BASH component merely for convenience.

# Uninstalling BASH

4D Insider allows you to uninstall the BASH component from your 4D database.

To uninstall BASH from your 4D database:

Using 4D Insider, open your database containing the copy of BASH to be uninstalled.

In the "Main" listing window, select the BASH component.

Consider again how great the BASH component is and make certain that you will *really* no longer need it in your 4D database.

Select the "Uninstall..." command in the "Components" menu.

This command is only active when a component is installed in the database. A dialog box appears allowing you to confirm or cancel the operation. If you uncertain about the previous step then the cancel option is probably your best choice at this time.

Click "OK" to validate the operation.

Remove the Affix\_BASH document and 4D Pack plugin from your 4DX folder.

Remove the call to the method *INIT\_BASH* from your On Startup database method.

All objects from the BASH component are deleted from your 4D database. Obviously, you are now very sad to no longer have the BASH component in your 4D database. Crying is allowed...

## Updating to BASH v1.5.9

Updating to the latest release of the BASH component is a simple procedure. Follow the instructions contained in the section **Installing and Updating BASH** to update the code within the structure.

In particular, for BASH v1.5.9, make certain that the latest release of the Affix BASH document is placed in the 4DX folder.

All previous copies of the 4D Pack plugin, v6.7.0, should be removed from the 4DX folders. Included in the archive with BASH v1.5.9 is a copy of 4D Pack v6.7.1 (entitled **4dp\_v671**) for both Macintosh and Windows. 4D Pack v6.7.1 should be placed in the platform appropriate 4DX folder next to your structure.



# Constants

There are a minimal number of custom constants included with the BASH component package. These constants are grouped into a few convenient constant groups for easier referencing and organization.

Where appropriate, it is highly recommended that the custom constants included with the BASH component be utilized within your code; this will simplify considerably future feature enhancements to the core code within BASH.

## URL Schemes

The URL Schemes constants group contains one constant for each of the supported URL schemes supported within the URL modules of the BASH component package. The following is a listing of the constants, and their values, within the URL Schemes constant group:

| <u>Constant</u>   | <u>Value</u> |
|-------------------|--------------|
| URL_Scheme_FTP    | 1            |
| URL_Scheme_HTTP   | 2            |
| URL_Scheme_Gopher | 3            |
| URL_Scheme_MailTo | 4            |
| URL_Scheme_News   | 5            |
| URL_Scheme_NNTP   | 6            |
| URL_Scheme_Telnet | 7            |
| URL_Scheme_File   | 8            |
| URL_Scheme_HTTPS  | 9            |

These constants are used only when initializing the URL module of the BASH component. See the section of this manual dealing with the URL module for more details on using the constants within the URL Schemes constants group.





# Modules

All of the code within the BASH component is organized into modules. Each module is designated by a three (3) to five (5) character module prefix. All of the module prefixes are used within the name of every object within the module (methods names, variable names, semaphore names, etc.). This allows for the easy identification of any object within the BASH component.

Each module contains a set of methods which can be used throughout your database once the BASH component is installed. Method names all begin with the module prefix followed by an underscore ("\_") characters. The remainder of the method name then describes the function of the method.

# ARR Module

The ARR Module is for managing and manipulating arrays within 4th Dimension. The ARR module includes routines for sizing arrays, inserting elements, converting between types of arrays, parsing of values into arrays, element cycling, and sort matching, among many others to come.



## ARR\_Add\_Elements\_to\_End

**ARR\_Add\_Elements\_to\_End** ( *Referenced Array*; *Elements to Add* )

**ARR\_Add\_Elements\_to\_End**  
(  
    -> *Referenced Array* : **Pointer**  
    -> *Elements to Add* : **Longint**  
)

| Parameter               | Type           | Description   |
|-------------------------|----------------|---|
| <i>Referenced Array</i> | <b>Pointer</b> | Reference to a single dimensional array of any type which will have a specified number of elements added to the end of it |
| <i>Elements to Add</i>  | <b>Longint</b> | Positive number of elements to add to the end of <i>Referenced Array</i>  |

The method **ARR\_Add\_Elements\_to\_End** will insert *Elements to Add* elements to the end of the array *Referenced Array*. Each element which is added to *Referenced Array* will be initialised to a **NULL** value.



## ARR\_Add\_Elements\_to\_Top

**ARR\_Add\_Elements\_to\_Top** ( *Referenced Array*; *Elements to Add* )

**ARR\_Add\_Elements\_to\_Top**  
(  
    -> *Referenced Array* : **Pointer**  
    -> *Elements to Add* : **Longint**  
)

)

| Parameter               | Type    | Description   |
|-------------------------|---------|---|
| <i>Referenced Array</i> | Pointer | Reference to a single dimensional array of any type which will have a specified number of elements added to the beginning of it |
| <i>Elements to Add</i>  | Longint | Positive number of elements to add to the beginning of <i>Referenced Array</i>  |

The method ***ARR\_Add\_Elements\_to\_Top*** will insert *Elements to Add* elements to the beginning of the array *Referenced Array*. Each element which is added to *Referenced Array* will be initialised to a **NULL** value.



## **ARR\_Clear**

***ARR\_Clear***( *Referenced Array*)

***ARR\_Clear***

(  
    -> *Referenced Array*: Pointer  
)

| Parameter               | Type    | Description   |
|-------------------------|---------|---|
| <i>Referenced Array</i> | Pointer | Reference to a single dimensional array of any type to be cleared |

The method ***ARR\_Clear*** will set the size of the array *Referenced Array* to zero (0). This will be done regardless of the type of array.

This command is equivalent to using native command **DELETE ELEMENT** to remove all of the elements of an array. ***ARR\_Clear*** will make certain though that *Referenced Array* is a valid array before clearing the array of all elements.



## **ARR\_Coerce\_from\_Text**

**ARR\_Coerce\_from\_Text** ( *Referenced Source Text Array ; Referenced Target Array* )

**ARR\_Coerce\_from\_Text**

(  
    -> *Referenced Source Text Array* : **Pointer**  
    -> *Referenced Target Array* : **Pointer**  
)

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Referenced Source Text Array</i> | <b>Pointer</b> | Referenced text array to coerce data from |
| <i>Referenced Target Array</i>      | <b>Pointer</b> | Referenced array to coerce data into      |

The method **ARR\_Coerce\_from\_Text** will coerce a series of values stored in a referenced text array into a separate referenced array of most any type. The target array is resized to contain the same number of elements as the source array, all elements including the zeroth (0th) element are coerced into the target array, and the array index is copied from the source to the target array.

*Referenced Source Text Array* is a pointer to the source text array to coerce values from.

*Referenced Target Array* is a pointer to the destination array which is to be resized and have its values coerced from text. Array types supported include string, text, boolean, date, integer, longint, real, and time.

**Note:** the method **ARR\_Coerce\_from\_Text** was added in BASH v1.5.5.



## **ARR\_Coerce\_to\_Text**

**ARR\_Coerce\_to\_Text** ( *Referenced Source Array ; Referenced Target Text Array* )

**ARR\_Coerce\_to\_Text**

(  
    -> *Referenced Source Array* : **Pointer**  
    -> *Referenced Target Text Array* : **Pointer**  
)

)

| Parameter                           | Type    | Description                               |
|-------------------------------------|---------|---|
| <i>Referenced Source Array</i>      | Pointer | Referenced array to coerce data from      |
| <i>Referenced Target Text Array</i> | Pointer | Referenced text array to coerce data into |

The method ***ARR\_Coerce\_to\_Text*** will coerce a series of values stored in a referenced array of most any type into a separate referenced text array. The target text array is resized to contain the same number of elements as the source array, all elements including the zeroth (0th) element are coerced into the target array, and the array index is copied from the source to the target text array.

*Referenced Source Array* is a pointer to the source array to coerce values from. Array types supported include string, text, boolean, date, integer, longint, real, and time.

*Referenced Target Array* is a pointer to the destination text array which is to be resized and have its values coerced to text.

**Note:** the method ***ARR\_Coerce\_to\_Text*** was added in BASH v1.5.5.



## **ARR\_Convert\_Longint\_to\_Text**

***ARR\_Convert\_Longint\_to\_Text***( *Referenced Longint Array*; *Referenced Text Array*)

***ARR\_Convert\_Longint\_to\_Text***

(  
    -> *Referenced Longint Array*: **Pointer**  
    -> *Referenced Text Array*: **Pointer**  
)

| Parameter                       | Type    | Description  |
|---------------------------------|---------|--|
| <i>Referenced Longint Array</i> | Pointer | Reference to a longint array holding values to convert |

|                              |                |   |
|------------------------------|----------------|---|
| <i>Referenced Text Array</i> | <b>Pointer</b> | Reference to text array which will hold textual equivalent of longint values from <i>Referenced Longint Array</i> . |
|------------------------------|----------------|---|

The method ***ARR\_Convert\_Longint\_to\_Text*** will convert all of the values in the array *Referenced Longint Array* to their textual equivalents and store them in *Referenced Text Array*. The size of *Referenced Text Array* will be set to be the same as *Referenced Longint Array*. Values will be converted element by element. The native **String** command is used to make the conversion of each element.

#### Usage:

This method is ideal for usage within interfaces in which numeric values must be selected from a list but the values must be text. This is often true when build a drop down interface item within HTML



### **ARR\_Convert\_Text\_to\_Longint**

***ARR\_Convert\_Text\_to\_Longint*** (*Referenced Text Array*; *Referenced Longint Array*)

***ARR\_Convert\_Text\_to\_Longint***

(  
     -> *Referenced Text Array*: **Pointer**  
     -> *Referenced Longint Array*: **Pointer**  
 )

| <b>Parameter</b>                | <b>Type</b>    | <b>Description</b>   |
|---------------------------------|----------------|--|
| <i>Referenced Text Array</i>    | <b>Pointer</b> | Reference to a text or string array containing values to convert |
| <i>Referenced Longint Array</i> | <b>Pointer</b> | Referenced to a longint array to contain converted values        |

The method ***ARR\_Convert\_Text\_to\_Longint*** will convert all of the elements of a referenced text or string array into 32 bit integers and place them into a referenced longint array. Elements are maintained in a well formed stack and the native **Int** and **Num 4D**

commands are used to make the conversion of each element.

*Referenced Text Array* is a pointer to the text array containing the elements to convert.

*Referenced Longint Array* is the destination array which is to contain the converted elements from *Referenced Text Array*. *Referenced Longint Array* will be resized to match the size of *Referenced Text Array*.

**Note:** the method *ARR\_Convert\_Text\_to\_Longint* was added in BASH v1.5.1.



## **ARR\_Convert\_Type\_to\_Longint**

**ARR\_Convert\_Type\_to\_Longint** (*Referenced Types Array*; *Referenced Longint Array*)

**ARR\_Convert\_Type\_to\_Longint**

(  
    -> *Referenced Types Array*: **Pointer**  
    -> *Referenced Longint Array*: **Pointer**  
)

| <b>Parameter</b>                | <b>Type</b>    | <b>Description</b>  |
|---------------------------------|----------------|---|
| <i>Referenced Types Array</i>   | <b>Pointer</b> | Reference to a text or string array containing type values to convert |
| <i>Referenced Longint Array</i> | <b>Pointer</b> | Referenced to a longint array to contain converted type values        |

The method *ARR\_Convert\_Type\_to\_Longint* will convert all of the elements of a referenced types array into 32 bit integers and place them into a referenced longint array. Elements are maintained in a well formed stack.

*Referenced Types Array* is a pointer to the text or string array containing the elements to convert.

*Referenced Longint Array* is the destination array which is to contain the converted elements from *Referenced*



*Types Array*. *Referenced Longint Array* will be resized to match the size of *Referenced Types Array*.

**Note:** a type array is any string or text array which is used to store standard Macintosh type codes. A type code can be any four (4) byte value used as a key of some sort on the Macintosh; this can include Macintosh creator codes, Macintosh file type codes, and resource type codes. See the section **Type Values**, below, for more information on Type values

**Note:** the method *ARR\_Convert\_Type\_to\_Longint* was added in BASH v1.5.1.



## **ARR\_Cycle\_Stack**

**ARR\_Cycle\_Stack** (*Referenced Array*; *Beginning Element*; *Ending Element*; *Cycle Count*)

**ARR\_Cycle\_Stack**

(  
-> *Referenced Array*: **Pointer**  
-> *Beginning Element*: **Longint**  
-> *Ending Element*: **Longint**  
-> *Cycle Count*: **Longint**  
)

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>                        |
|--------------------------|----------------|---|
| <i>Referenced Array</i>  | <b>Pointer</b> | Referenced array to cycle elements within |
| <i>Beginning Element</i> | <b>Longint</b> | Element number to begin cycle at          |
| <i>Ending Element</i>    | <b>Longint</b> | Element number to end cycle at            |
| <i>Cycle Count</i>       | <b>Longint</b> | Number of elements to cycle               |

The method *ARR\_Cycle\_Stack* will cycle a specified range of elements, as specified by *Beginning Element* and *Ending Element*, in the array *Referenced Array* a number of elements. The direction of the cycle and the number of elements cycled is determined by *Cycle Count*.

If *Cycle Count* is less than zero (0), elements in the array range are cycled towards the beginning of *Referenced*

*Array*. If *Cycle Count* is greater than zero (0), elements in the array range are cycled towards the ending of *Referenced Array*.

### Example:

Assume the array **axMyArray** has the following elements:

|              |           |
|--------------|-----------|
| axMyArray{1} | Andrew    |
| axMyArray{2} | Bobby     |
| axMyArray{3} | Carolyn   |
| axMyArray{4} | Debby     |
| axMyArray{5} | Evelyn    |
| axMyArray{6} | Frederick |
| axMyArray{7} | Guido     |

After making the call:

**ARR\_Cycle\_Stack** (->axMyArray; 2; 5 1)

the array **axMyArray** would now have the following elements:

|              |           |
|--------------|-----------|
| axMyArray{1} | Andrew    |
| axMyArray{2} | Carolyn   |
| axMyArray{3} | Debby     |
| axMyArray{4} | Evelyn    |
| axMyArray{5} | Bobby     |
| axMyArray{6} | Frederick |
| axMyArray{7} | Guido     |

Subsequently, if the call:

**ARR\_Cycle\_Stack** (->axMyArray; 4; 7 -2)

were to be made, the array **axMyArray** would then have the following elements:

|              |           |
|--------------|-----------|
| axMyArray{1} | Andrew    |
| axMyArray{2} | Carolyn   |
| axMyArray{3} | Debby     |
| axMyArray{4} | Frederick |

|              |        |
|--------------|--------|
| axMyArray{5} | Guido  |
| axMyArray{6} | Evelyn |
| axMyArray{7} | Bobby  |

### Usage:

This method is exceedingly useful in interfaces in which elements in a scrollable array can be subject to drag and drop reordering of elements. Elements can be cycled within the array with a single method call.



## ARR\_ERROR

**ARR\_ERROR** (*BASH Error Number; Special Error Text; Calling Method Name*)

### ARR\_ERROR

```
(
    -> BASH Error Number: Longint
    -> Special Error Text: Text
    -> Calling Method Name: Text
)
```

| Parameter                  | Type    | Description   |
|----------------------------|---------|---|
| <i>BASH Error Number</i>   | Longint | Internal BASH error number                              |
| <i>Special Error Text</i>  | Text    | Special text to describe the exact error instance       |
| <i>Calling Method Name</i> | Text    | Name of the method that the error condition occurred in |

The method **ARR\_ERROR** acts as a callback method from within the ARR module for errors that may occur. Any time an error condition is detected within the ARR module, a call to the method **ARR\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the ARR method which call the **ARR\_ERROR** method.

The **ARR\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.



## **ARR\_Find\_First\_Binary**

**ARR\_Find\_First\_Binary** (*Referenced Array ; Referenced Value* ) =>  
*Found Index*

**ARR\_Find\_First\_Binary**  
(  
    -> *Referenced Array* : **Pointer**  
    -> *Referenced Value* : **Pointer**  
)  
=> *Found Index* : **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>  |
|-------------------------|----------------|---|
| <i>Referenced Array</i> | <b>Pointer</b> | Pointer to an array which is going to be searched using a binary search algorithm |
| <i>Referenced Value</i> | <b>Pointer</b> | Value to search for   |
| <i>Found Index</i>      | <b>Longint</b> | Index of first element found matching specified value                             |

The method **ARR\_Find\_First\_Binary** runs a binary search on a referenced array for a referenced value and returns the index of the first element matching. Of course, since the search performed is a binary search, the values within the specified referenced array must be sorted; this method assumes that the values in the specified referenced array are already sorted.

*Referenced Array* is a pointer to an array which is already sorted and is to be searched.

*Referenced Value* is a pointer to a value which is to be searched for within *Referenced Array*.

*Found Index* is the index of the first element within *Referenced Array* that matches *Referenced Value* .

**Note:** the method *ARR\_Find\_First\_Binary* was added in BASH v1.5.9.



## **ARR\_Find\_Last\_Same**

**ARR\_Find\_Last\_Same** ( *Referenced Array* ; *Start Index* ) => *Last Match Index*

**ARR\_Find\_Last\_Same**  
(  
    -> *Referenced Array* : **Pointer**  
    -> *Start Index* : **Longint**  
)  
=> *Last Match Index* : **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>   |
|-------------------------|----------------|--|
| <i>Referenced Array</i> | <b>Pointer</b> | Pointer to an array which is going to be sequentially scanned              |
| <i>Start Index</i>      | <b>Longint</b> | Index to begin scan at   |
| <i>Last Match Index</i> | <b>Longint</b> | Index of last element sequentially found matching <i>Start Index</i> value |

The method *ARR\_Find\_Last\_Same* will sequentially scan a specified array starting at a specified starting index and return the first following element which has a value different from the value of the specified starting index.

*Referenced Array* is a pointer to an array which is to be sequentially scanned.

*Start Index* is the index which is to be the beginning of the sequential element scan of array values.

*Last Match Index* is the index of the first element following *Start Index* within *Referenced Array* which has the same value of that within *Start Index* .

Note: the method **ARR\_Find\_Last\_Same** was added in BASH v1.5.9.



## **ARR\_Order\_to\_Match**

**ARR\_Order\_to\_Match** (*Referenced Ordered Array; Referenced Match Array*  
*{; Parallel Array {; ... } }* )

### **ARR\_Order\_to\_Match**

```
(  
    -> Referenced Ordered Array: Pointer  
    -> Referenced Match Array: Pointer  
    { -> Parallel Array: Pointer }  
)
```

| Parameter                       | Type    | Description   |
|---------------------------------|---------|---|
| <i>Referenced Ordered Array</i> | Pointer | Referenced array holding longint values sorted as desired   |
| <i>Referenced Match Array</i>   | Pointer | Referenced array holding longint values which should be ordered to match the sorting within the <i>Referenced Order Array</i>         |
| <i>Parallel Array</i>           | Pointer | Up to five (5) more optional array references which will be kept in parallel with the reordering of the <i>Referenced Match Array</i> |

The method **ARR\_Order\_to\_Match** will reorder a series of arrays to match the ordering within *Referenced Ordered Array*. The reordering will be done by matching the values in *Referenced Match Array* with values stored in *Referenced Ordered Array*, keeping all of the optional *Parallel Array* elements row-wise in line with the *Referenced Match Array*.

### **Example:**

Assume the following arrays:

|                   |   |
|-------------------|---|
| aiOrderedLong {1} | 2 |
| aiOrderedLong {2} | 5 |
| aiOrderedLong {3} | 7 |
| aiOrderedLong {4} | 9 |

|                |       |
|----------------|-------|
| aiMatchLong{1} | 7     |
| aiMatchLong{2} | 9     |
| aiMatchLong{3} | 2     |
| aiMatchLong{4} | 5     |
|                |       |
| axWhatever{1}  | seven |
| axWhatever{2}  | nine  |
| axWhatever{3}  | two   |
| axWhatever{4}  | five  |

After making the following call:

```
ARR_Order_to_Match (->aiOrderedLong;
                    ->aiMatchLong; ->axWhatever)
```

the same three arrays would now be:

|                   |       |
|-------------------|-------|
| aiOrderedLong {1} | 2     |
| aiOrderedLong {2} | 5     |
| aiOrderedLong {3} | 7     |
| aiOrderedLong {4} | 9     |
|                   |       |
| aiMatchLong{1}    | 2     |
| aiMatchLong{2}    | 5     |
| aiMatchLong{3}    | 7     |
| aiMatchLong{4}    | 9     |
|                   |       |
| axWhatever{1}     | two   |
| axWhatever{2}     | five  |
| axWhatever{3}     | seven |
| axWhatever{4}     | nine  |

### Usage:

This method is very useful for keeping array synchronised when the elements may be subject to reordering. By keeping a single key array into the stack, all of the columns within the stack can be kept together row-wise with a single method call. This method is ideal for use with interfaces that involve scrollable arrays which can be reordered through drag and drop.



## **ARR\_Pack\_to\_Text**

**ARR\_Pack\_to\_Text** (*Referenced Values Array* ; *Delimiter Value* ) =>  
*Packed Text*

### **ARR\_Pack\_to\_Text**

(  
    -> *Referenced Values Array*: **Pointer**  
    -> *Delimiter Value*: **Text**  
)  
=> *Packed Text*: **Text**

| <b>Parameter</b>               | <b>Type</b>    | <b>Description</b>   |
|--------------------------------|----------------|--|
| <i>Referenced Values Array</i> | <b>Pointer</b> | Reference to a text, string, date, longint, integer, or real array containing values to pack     |
| <i>Delimiter Value</i>         | <b>Text</b>    | Delimiter value to place between elements being packed   |
| <i>Packed Text</i>             | <b>Text</b>    | Packed elements from <i>Referenced Values Array</i> which are separate by <i>Delimiter Value</i> |

The method **ARR\_Pack\_to\_Text** will pack the elements from a referenced array into a text value separated by a specified delimiter value.

*Referenced Values Array* is a text, string, date, longint, integer, or real array containing values which are going to be packed. Before packing, each element is coerced to text.

*Delimiter Value* is a character or string which is placed between each value from *Referenced Values Array* when packed.

*Packed Text* is the resulting values all packed into a single text variable.

**Note:** the method **ARR\_Pack\_to\_Text** was added in BASH v1.5.1.





## ARR\_Populate\_Text\_Array

**ARR\_Populate\_Text\_Array** ( *Referenced Text Array* {; *Fill Text* {; ... } } )

**ARR\_Populate\_Text\_Array**

```
(
    -> Referenced Text Array: Pointer
    { -> Fill Text: Text }
)
```

| Parameter                    | Type           | Description  |
|------------------------------|----------------|--|
| <i>Referenced Text Array</i> | <b>Pointer</b> | Text array to be filled by specified text values                         |
| <i>Fill Text</i>             | <b>Text</b>    | Optional number of text values to fill into <i>Referenced Text Array</i> |

The method **ARR\_Populate\_Text\_Array** provides a simple mechanism to popular many text values into a text array. *Referenced Text Array* is resized so the number of elements match the number of *Fill Text* values which are passed to the method. The only limitation on the number of *Fill Text* values which can be passed to **ARR\_Populat\_Text\_Array** is that which is imposed by the development environment.



---

## ARR\_Remove\_Elements\_from\_End

**ARR\_Remove\_Elements\_from\_End** ( *Referenced Array*; *Elements to Remove* )

**ARR\_Remove\_Elements\_from\_End**

```
(
    -> Referenced Array: Pointer
    -> Elements to Remove: Longint
)
```

| Parameter               | Type           | Description   |
|-------------------------|----------------|---|
| <i>Referenced Array</i> | <b>Pointer</b> | Reference to a single dimensional array of any type which will have a specified number of elements removed from the end of it |

|                           |                |  |
|---------------------------|----------------|--|
| <i>Elements to Remove</i> | <b>Longint</b> | <b>Positive number of elements to remove from the end of <i>Referenced Array</i></b> |
|---------------------------|----------------|--|

The method ***ARR\_Remove\_Elements\_from\_End*** will remove *Elements to Remove* elements from the end of the array *Referenced Array*.

---

## **ARR\_Remove\_Elements\_from\_Top**

***ARR\_Remove\_Elements\_from\_Top*** ( *Referenced Array*; *Elements to Remove* )

***ARR\_Remove\_Elements\_from\_Top***  
 (  
     -> *Referenced Array*: **Pointer**  
     -> *Elements to Remove*: **Longint**  
 )

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>  |
|---------------------------|----------------|---|
| <i>Referenced Array</i>   | <b>Pointer</b> | Reference to a single dimensional array of any type which will have a specified number of elements removed from the beginning of it |
| <i>Elements to Remove</i> | <b>Longint</b> | Positive number of elements to remove form the beginning of <i>Referenced Array</i>   |

The method ***ARR\_Remove\_Elements\_from\_Top*** will remove *Elements to Remove* elements from the beginning of the array *Referenced Array*.

---

## **ARR\_Set\_Size**

***ARR\_Set\_Size*** ( *Referenced Array*; *New Maximum Element Number* )

***ARR\_Set\_Size***  
 (  
     -> *Referenced Array*: **Pointer**  
     -> *New Maximum Element Number*: **Longint**  
 )

| Parameter                         | Type    | Description   |
|-----------------------------------|---------|---|
| <i>Referenced Array</i>           | Pointer | Reference to a single dimensional array of any type which will be resized     |
| <i>New Maximum Element Number</i> | Longint | New maximum element number which <i>Referenced Array</i> should be resized to |

The method ***ARR\_Set\_Size*** will resized the array *Referenced Array* to have a maximum element number of *New Maximum Element Number*. If new elements are added to *Referenced Array*, they will be added to the end of the array and will have all elements initialized to NULL.



## **ARR\_Set\_Sizes**

***ARR\_Set\_Sizes*** (*New Maximum Element Number* ; *Referenced Array* { ; *Referenced Array* { ; ... } } )

### ***ARR\_Set\_Sizes***

```
(
    -> New Maximum Element Number : Longint
    -> Referenced Array : Pointer
    {-> Referenced Array : Pointer}
)
```

| Parameter                         | Type    | Description   |
|-----------------------------------|---------|---|
| <i>New Maximum Element Number</i> | Longint | New maximum element number which <i>Referenced Arrays</i> should be resized to        |
| <i>Referenced Array</i>           | Pointer | References to one or more single dimensional arrays of any type which will be resized |

The method ***ARR\_Set\_Sizes*** will resized one or more arrays *Referenced Array* to have a maximum element number of *New Maximum Element Number*. If new elements are added to the *Referenced Array* arrays, they will be added to the end of the arrays and will have all elements initialized to NULL.

This method is functionally equivalent to *ARR\_Set\_Size* except that it provides for the ability to resize multiple arrays, all to the same size, with a single method call.

**Note:** the method *ARR\_Set\_Sizes* was added in BASH v1.5.4.

# BLOB Module

The BLOB module provides basic operations on BLOBs. With the current release of the BASH component, the BLOB module basically just provides ancillary functionality which is used in other modules. In future versions of the BASH component, the BLOB module will be expanded considerably.



## BLOB\_Append\_Text

**BLOB\_Append\_Text** ( *Referenced BLOB* ; *Text to Append* )

**BLOB\_Append\_Text**

(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Text to Append* : **Text**  
)

| Parameter              | Type           | Description   |
|------------------------|----------------|---|
| <i>Referenced BLOB</i> | <b>Pointer</b> | <b>Pointer to BLOB to append to</b>                   |
| <i>Text to Append</i>  | <b>Text</b>    | <b>Text value to append to <i>Referenced BLOB</i></b> |

The method **BLOB\_Append\_Text** will append a specified text value to a referenced BLOB. The text is appended directly to the end of the BLOB without adding any variable indicator or length values.

*Referenced BLOB* is a pointer to a BLOB to append text to.

*Text to Append* is the text value to append to *Referenced BLOB*.

**Note:** the method **BLOB\_Append\_Text** was added in BASH v1.5.3.



## BLOB\_BLOB\_to\_Document

***BLOB\_BLOB\_to\_Document*** ( *Referenced BLOB* ; *Full Document Path* ) =>  
*Error Status*

***BLOB\_BLOB\_to\_Document***  
(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Full Document Path* : **Text**  
)  
=> *Error Status* : **Longint**

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>   |
|---------------------------|----------------|--|
| <i>Referenced BLOB</i>    | <b>Pointer</b> | Reference to BLOB containing data fork of document                       |
| <i>Full Document Path</i> | <b>Text</b>    | Full path to document to contain <i>Referenced BLOB</i> as the data fork |
| <i>Error Status</i>       | <b>Longint</b> | qi for document data fork written successfully                           |

The method ***BLOB\_BLOB\_to\_Document*** will write referenced data fork contents to a document specified by a full path. If the document specified, and any of the enclosing directories in the path to the document do not exist, this method will create them.

*Referenced BLOB* is a pointer to a BLOB containing the data fork to be written into the document.

*Full Document Path* is the full path to the document to be written.

*Error Status* is the indicator for whether this routine successfully created the full path the document, if needed, created the document, if needed, and wrote the contents of *Referenced BLOB* into the data fork of the document specified by *Full Document Path*. *Error Status* will be zero (0) if the operation was successful; *Error Status* will be one (1) if the operation failed at any point.

**Note:** the method ***BLOB\_BLOB\_to\_Document*** was added in BASH v1.5.4.



## BLOB\_Change\_Case

**BLOB\_Change\_Case** ( *Referenced BLOB* ; *Starting Offset* ; *Bytes to Scan* ; *Case Flag* )

**BLOB\_Change\_Case**

(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Starting Offset* : **Longint**  
    -> *Bytes to Scan* : **Longint**  
    -> *Case Flag* : **Longint**  
)

| Parameter              | Type           | Description   |
|------------------------|----------------|---|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Pointer to BLOB to change the case of contents                              |
| <i>Starting Offset</i> | <b>Longint</b> | Offset of first byte to possibly change case of                             |
| <i>Bytes to Scan</i>   | <b>Longint</b> | Number of bytes following <i>Starting Offset</i> to possibly change case of |
| <i>Case Flag</i>       | <b>Longint</b> | Flag to indicate whether to first bytes to uppercase or lowercase           |

The method **BLOB\_Change\_Case** will scan a specified byte range within a specified BLOB and force bytes to either uppercase or lowercase.

*Referenced BLOB* is a pointer to the BLOB to use to scan the contents of for changing case.

*Starting Offset* is the starting offset within *Referenced BLOB* to begin scanning bytes to check if the case should be changed. This value should be set to zero (0) to begin scanning *Referenced BLOB* from the beginning.

*Bytes to Scan* is the number of bytes within *Referenced BLOB* to scan. This value should be set to MAXLONG to scan through to the end of *Referenced BLOB*.

*Case Flag* is a flag to indicate whether case of bytes should be changed to uppercase or lowercase. Set this value to one (1) to change all bytes to uppercase; set this value to two (2) to change all bytes to lowercase.

Note: the method *BLOB\_Change\_Case* was added in BASH v1.5.9.



## BLOB\_Clear

**BLOB\_Clear** ( *Referenced BLOB* )

**BLOB\_Clear**

(  
    -> *Referenced BLOB* : **Pointer**  
)

| Parameter              | Type           | Description              |
|------------------------|----------------|--------------------------|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Pointer to BLOB to clear |

The method *BLOB\_Clear* will clear completely the contents of a referenced BLOB. This method is functionally equivalent to calling the native 4D command **SET BLOB SIZE** with a size value of zero (0).

*Referenced BLOB* is a pointer to the BLOB to clear.

Note: the method *BLOB\_Clear* was added in BASH v1.5.3.



## BLOB\_Document\_to\_BLOB

**BLOB\_Document\_to\_BLOB** ( *Referenced BLOB* ; *Full Document Path* ) =>  
    *Error Status*

**BLOB\_Document\_to\_BLOB**

(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Full Document Path* : **Text**  
)  
    => *Error Status* : **Longint**

| Parameter                 | Type           | Description   |
|---------------------------|----------------|---|
| <i>Referenced BLOB</i>    | <b>Pointer</b> | Reference to BLOB to contain data fork of document specified        |
| <i>Full Document Path</i> | <b>Text</b>    | Full path to document to read data fork into <i>Referenced BLOB</i> |



|                     |                |   |
|---------------------|----------------|---|
| <i>Error Status</i> | <i>Longint</i> | qi for document data fork read successfully |
|---------------------|----------------|---|

The method ***BLOB\_Document\_to\_BLOB*** will read data fork contents of a document specified by a full path into a referenced BLOB variable.

*Referenced BLOB* is a pointer to a BLOB to contain the data fork of a document read.

*Full Document Path* is the full path to the document to be read.

*Error Status* is the indicator for whether this routine successfully read the data fork of the document specified by *Full Document Path* into *Referenced BLOB*. *Error Status* will be zero (0) if the operation was successful; *Error Status* will be one (1) if the operation failed at any point.

**Note:** the method ***BLOB\_Document\_to\_BLOB*** was added in BASH v1.5.4.



## **BLOB\_Find\_Between\_Folding\_x**

***BLOB\_Find\_Between\_Folding\_x*** ( *Referenced BLOB* ; *Starting Offset* ; *Referenced Ending Offset* ; *Begin String* ; *End String* ; *Folding Characters* ) => *asd*

### ***BLOB\_Find\_Between\_Folding\_x***

```
(
    -> Referenced BLOB : Pointer
    -> Starting Offset : Longint
    -> Referenced Ending Offset : Pointer
    -> Begin String : Text
    -> End String : Text
    -> Folding Characters : Text
)
=> Found Text : Text
```

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>                     |
|------------------------|----------------|--|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Reference to a BLOB contents to search |

|                                 |                |  |
|---------------------------------|----------------|--|
| <i>Starting Offset</i>          | <b>Longint</b> | <b>Starting byte offset within <i>Referenced BLOB</i> to begin search</b>  |
| <i>Referenced Ending Offset</i> | <b>Pointer</b> | <b>Referenced longint to contain the byte offset immediately following the found value</b>   |
| <i>Begin String</i>             | <b>Text</b>    | <b>Text to find to mark the beginning of the found value</b>   |
| <i>End String</i>               | <b>Text</b>    | <b>Text to find to mark the ending of the found value</b>  |
| <i>Folding Characters</i>       | <b>Text</b>    | <b>Text to delineate a folded content</b>  |
| <i>Found Text</i>               | <b>Text</b>    | <b>Return text found in <i>Referenced BLOB</i> after <i>Starting Offset</i> and between <i>Begin String</i> and <i>End String</i> , inclusively, with any folded values matching delineated by <i>Folding Characters</i></b> |

The method ***BLOB\_Find\_Between\_Folding\_x*** will return the text found after a specified byte offset which falls after a specified beginning string, up to a specified end string, within a specified BLOB value, inclusively. Content which is valid folding content will be included in the resulting found text.

The search within *Referenced BLOB* will begin with the *Starting Offset* byte value. *Referenced BLOB* will then be scanned until *Begin String* is found. Once *Begin String* is found following *Starting Offset* in *Referenced BLOB* , the contents after *Begin String* will be returned, up to but not including *Ending String* (or the end of *Referenced BLOB* if *Ending String* is not found).

If immediately following the found *End String* instance is a match for *Folding Characters* , thereby indicating a folded line, then *Referenced BLOB* is searched further for the next occurrence of *End String* to mark the end of the found content. The found content will be returned up to, but not including, the final instance of *End String* which does not proceed a match for *Folding Characters* , or the end of *Referenced BLOB* .

The search is done sequentially and is not case sensitive.

The byte offset immediately following the first non-folding *Ending String* for the found value will be returned in the referenced parameter *Referenced Ending Offset* .

*Referenced BLOB* is a reference to a BLOB value to be searched through.

*Starting Offset* is the first byte offset within *Referenced BLOB* which is to be searched sequentially for *Begin String* .

*Referenced Ending Offset* is a reference to a longint to hold the byte offset value immediately following *End String* following *Found Text* extracted from *Referenced BLOB* .

*Begin String* is the string of characters to search for within *Referenced BLOB* beginning at *Starting Offset* to delineate the beginning of the found value.

*End String* is the string of characters to be used as the ending delimiter for the found value. If *End String* is not found following *Begin String* or all found *End String* values are followed immediately by *Folding Characters* , the resulting found text will include the whole contents up to the end of *Referenced BLOB* (barring overflow conditions).

*Folding Characters* is the value to check for immediately following each instance of *End String* to indicate a folding line of content. Folded lines are considered valid contents of *Found Text* and are included as such with all returned values for this method.

*Found Text* is the found text value matching all of the search criteria provided and detailed, above.

**Note:** the method *BLOB\_Find\_Between\_Folding\_x* was added in BASH v1.5.4.



## **BLOB\_Find\_Between\_x**

**BLOB\_Find\_Between\_x** ( *Referenced BLOB ; Starting Offset ; Referenced Ending Offset ; Begin String ; End String* ) => *Found Text*

### **BLOB\_Find\_Between\_x**

```

(
    -> Referenced BLOB : Pointer
    -> Starting Offset : Longint
    -> Referenced Ending Offset : Pointer
    -> Begin String : Text
    -> End String : Text
)
=> Found Text : Text

```

| <b>Parameter</b>                | <b>Type</b>    | <b>Description</b>   |
|---------------------------------|----------------|--|
| <i>Referenced BLOB</i>          | <b>Pointer</b> | Reference to a BLOB contents to search   |
| <i>Starting Offset</i>          | <b>Longint</b> | Starting byte offset within <i>Referenced BLOB</i> to begin search   |
| <i>Referenced Ending Offset</i> | <b>Pointer</b> | Referenced longint to contain the byte offset immediately following the found value  |
| <i>Begin String</i>             | <b>Text</b>    | Text to find to mark the beginning of the found value  |
| <i>End String</i>               | <b>Text</b>    | Text to find to mark the ending of the found value   |
| <i>Found Text</i>               | <b>Text</b>    | Return text found in <i>Referenced BLOB</i> after <i>Starting Offset</i> and between <i>Begin String</i> and <i>End String</i> , inclusively |

The method **BLOB\_Find\_Between\_x** will return the text found after a specified byte offset which falls after a specified beginning string, up to a specified end string, within a specified BLOB value.

The search within *Referenced BLOB* will begin with the *Starting Offset* byte value. *Referenced BLOB* will then be scanned until *Begin String* is found. Once *Begin String* is found following *Starting Offset* in *Referenced BLOB* , the contents after *Begin String* will be returned, up to but not including *Ending String* (or the end of *Referenced BLOB* if *Ending String* is not found).

The search is done sequentially and is not case sensitive.

The byte offset immediately following *Ending String* for the found value will be returned in the referenced parameter *Referenced Ending Offset* .

*Referenced BLOB* is a reference to a BLOB value to be searched through.

*Starting Offset* is the first byte offset within *Referenced BLOB* which is to be searched sequentially for *Begin String* .

*Referenced Ending Offset* is a reference to a longint to hold the byte offset value immediately following the *Ending String* following *Found Text* extracted from *Referenced BLOB* .

*Begin String* is the string of characters to search for within *Referenced BLOB* beginning at *Starting Offset* to delineate the beginning of the found value.

*End String* is the string of characters to be used as the ending delimiter for the found value. If *End String* is not found following *Begin String* , the resulting found text will include the whole contents up to the end of *Referenced BLOB* (barring overflow conditions).

*Found Text* is the found text value matching all of the search criteria provided, above.

**Note:** the method *BLOB\_Find\_Between\_x* was added in BASH v1.5.4.



## **BLOB\_Find\_Text\_Case**

**BLOB\_Find\_Text\_Case** ( *Search Text* ; *Referenced BLOB* ; *Beginning Offset* ;  
*Search Range Byte Count* ) => *Found Offset*

**BLOB\_Find\_Text\_Case**  
(

-> *Search Text* : **Text**  
 -> *Referenced BLOB* : **Pointer**  
 -> *Beginning Offset* : **Longint**  
 -> *Search Range Byte Count* : **Longint**  
 )  
 => *Found Offset*: **Longint**

| <b>Parameter</b>               | <b>Type</b>    | <b>Description</b>   |
|--------------------------------|----------------|--|
| <i>Search Text</i>             | <b>Text</b>    | Text value to search for   |
| <i>Referenced BLOB</i>         | <b>Pointer</b> | Pointer to BLOB to search for <i>Search Text</i> within  |
| <i>Beginning Offset</i>        | <b>Longint</b> | Offset to byte within <i>Referenced BLOB</i> to begin search for <i>Search Text</i>                                |
| <i>Search Range Byte Count</i> | <b>Longint</b> | Total number of bytes within <i>Referenced BLOB</i> in which the search should be performed                        |
| <i>Found Offset</i>            | <b>Longint</b> | Byte offset within <i>Referenced BLOB</i> after <i>Beginning Offset</i> in which <i>Search Text</i> is first found |

The method ***BLOB\_Find\_Text\_Case*** will perform a sequential, case sensitive search for a specified text value within a referenced BLOB value, within a range of bytes, and return the offset of the first occurrence found.

The search is done sequentially from the specified beginning byte offset. It will continue sequential up to, but not past, the number of bytes specified.

*Search Text* is the text value to search for within *Referenced BLOB*.

*Referenced BLOB* is a pointer to a BLOB value which will be searched.

*Beginning Offset* is the byte offset within *Referenced BLOB* to begin the search for *Search Text*. If the search is to be done from the beginning of *Referenced BLOB*, pass zero (0) as the value for *Beginning Offset*.

*Search Range Byte Count* is the number of bytes past *Beginning Offset* within *Referenced BLOB* in which the value *Search Text* should be searched for. The search

will terminate after *Search Range Byte Count* if no match is found. To search until the end of *Referenced BLOB*, pass MaxLong as the value for *Search Range Byte Count*.

*Found Offset* is the byte offset within *Referenced BLOB* which *Search Text* is first found after *Beginning Offset* and before *Search Range Byte Offset* bytes. If no match is found within the referenced BLOB value within the specified range, *Found Offset* will be -1.

**Note:** the method *BLOB\_Find\_Text\_Case* was added in BASH v1.5.7.



## **BLOB\_Find\_Byte**

**BLOB\_Find\_Byte** ( ASCII Value to Find ; Referenced BLOB ; Starting Offset ; Byte Count to Search ) => Found Offset

### **BLOB\_Find\_Byte**

```
(
    -> ASCII Value to Find : Longint
    -> Referenced BLOB : Pointer
    -> Starting Offset : Longint
    -> Byte Count to Search : Longint
)
=> Found Offset : Longint
```

| Parameter            | Type    | Description  |
|----------------------|---------|--|
| ASCII Value to Find  | Longint | ASCII value to search for  |
| Referenced BLOB      | Pointer | Pointer to BLOB to scan  |
| Starting Offset      | Longint | Beginning offset within Referenced BLOB to start scanning            |
| Byte Count to Search | Longint | Number of bytes after Starting Offset within Referenced BLOB to scan |
| Found Offset         | Longint | Offset of first byte within range matching ASCII Value to Find       |

The method *BLOB\_Find\_Byte* will find a particular byte value within a specified referenced BLOB within a specified byte range within the BLOB and will return the offset of the found byte.

*ASCII Value to Find* is the ASCII value of the byte to scan for.

*Referenced BLOB* is a pointer to a BLOB to search through.

*Starting Offset* is the offset within *Referenced BLOB* to begin scanning for *ASCII Value to Find* . Pass a value of zero (0) to begin search at the first byte within the referenced BLOB.

*Byte Count to Search* is the number of bytes following *Starting Offset* within *Referenced BLOB* which will be scanned for a matching *ASCII Value to Find* . If the complete length of the referenced BLOB is to be searched then pass a value of MAXLONG for this parameter.

*Found Offset* is the offset within the referenced BLOB of the first byte within the offset range specified that match *ASCII Value to Find* . If no matching byte was found within the specified offset range, *Found Offset* will be set to negative one (-1).

**Note:** the method *BLOB\_Find\_Byte* was added in BASH v1.5.8.



## **BLOB\_Find\_Text\_NonCase**

***BLOB\_Find\_Text\_NonCase*** ( *Search Text* ; *Referenced BLOB* ; *Beginning Offset* ; *Search Range Byte Count* ) => *Found Offset*

***BLOB\_Find\_Text\_NonCase***

(  
-> *Search Text* : **Text**  
-> *Referenced BLOB* : **Pointer**  
-> *Beginning Offset* : **Longint**  
-> *Search Range Byte Count* : **Longint**  
)  
=> *Found Offset*: **Longint**

| <b>Parameter</b> | <b>Type</b> | <b>Description</b> |
|------------------|-------------|--------------------|
|------------------|-------------|--------------------|



|                                |                |   |
|--------------------------------|----------------|---|
| <i>Search Text</i>             | <b>Text</b>    | <b>Text</b> value to search for   |
| <i>Referenced BLOB</i>         | <b>Pointer</b> | <b>Pointer</b> to BLOB to search for <i>Search Text</i> within  |
| <i>Beginning Offset</i>        | <b>Longint</b> | <b>Offset</b> to byte within <i>Referenced BLOB</i> to begin search for <i>Search Text</i>                                |
| <i>Search Range Byte Count</i> | <b>Longint</b> | <b>Total number of bytes</b> within <i>Referenced BLOB</i> in which the search should be performed                        |
| <i>Found Offset</i>            | <b>Longint</b> | <b>Byte offset</b> within <i>Referenced BLOB</i> after <i>Beginning Offset</i> in which <i>Search Text</i> is first found |

The method ***BLOB\_Find\_Text\_NonCase*** will perform a sequential, non-case sensitive search for a specified text value within a referenced BLOB value, within a range of bytes, and return the offset of the first occurrence found.

The search is done sequentially from the specified beginning byte offset. It will continue sequential up to, but not past, the number of bytes specified.

*Search Text* is the text value to search for within *Referenced BLOB*.

*Referenced BLOB* is a pointer to a BLOB value which will be searched.

*Beginning Offset* is the byte offset within *Referenced BLOB* to begin the search for *Search Text*. If the search is to be done from the beginning of *Referenced BLOB*, pass zero (0) as the value for *Beginning Offset*.

*Search Range Byte Count* is the number of bytes past *Beginning Offset* within *Referenced BLOB* which the value *Search Text* should be searched for. The search will terminate after *Search Range Byte Count* if no match is found. To search until the end of *Referenced BLOB*, pass MaxLong as the value for *Search Range Byte Count*.

*Found Offset* is the byte offset within *Referenced BLOB* which *Search Text* is first found after *Beginning Offset*

and before *Search Range Byte Offset* bytes. If no match is found within the referenced BLOB value within the specified range, *Found Offset* will be -1.

**Note:** the method *BLOB\_Find\_Text\_NonCase* was added in BASH v1.5.4.



## **BLOB\_Finds\_Between\_Folding\_x**

***BLOB\_Finds\_Between\_Folding\_x*** ( *Referenced BLOB* ; *Begin String* ; *End String* ; *Folding Characters* ) => *Found Text*

***BLOB\_Finds\_Between\_Folding\_x***  
(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Begin String* : **Text**  
    -> *End String* : **Text**  
    -> *Folding Characters* : **Text**  
)  
    => *Found Text* : **Text**

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>   |
|---------------------------|----------------|--|
| <i>Referenced BLOB</i>    | <b>Pointer</b> | Reference to a BLOB contents to search   |
| <i>Begin String</i>       | <b>Text</b>    | Text to find to mark the beginning of the found value  |
| <i>End String</i>         | <b>Text</b>    | Text to find to mark the ending of the found value   |
| <i>Folding Characters</i> | <b>Text</b>    | Text to delineate a folded content   |
| <i>Found Text</i>         | <b>Text</b>    | Return text found in <i>Referenced BLOB</i> between <i>Begin String</i> and <i>End String</i> , inclusively, with any folded values matching delineated by <i>Folding Characters</i> |

The method ***BLOB\_Finds\_Between\_Folding\_x*** will return the concatenated all text found which falls between a specified beginning string and ending string, within a specified BLOB value, inclusively. Content which is valid folding content will be included in the resulting found text.

This method operates exactly the same as the method ***BLOB\_Find\_Between\_Folding\_x*** , detailed above, except that it is done across the complete contents of *Referenced BLOB* and all content, including folded lines, which is between *Begin String* and *End String* is returned. This includes multiple occurrences of content which may match the delimiter and folding conditions.

The search is done sequentially and is not case sensitive.

*Referenced BLOB* is a reference to a BLOB value to be searched through.

*Begin String* is the string of characters to mark the beginning of content within *Referenced BLOB* .

*End String* is the string of characters to be used as the ending delimiter for content within *Referenced BLOB* .

*Folding Characters* is the value to check for immediately following each instance of *End String* to indicate a folding line of content. Folded lines are considered valid contents of *Found Text* and are included as such with all returned values for this method.

*Found Text* is the found text value matching all of the search criteria provided and detailed, above.

**Note:** the method ***BLOB\_Finds\_Between\_Folding\_x*** was added in BASH v1.5.4.



## **BLOB\_Replace\_Byte**

***BLOB\_Replace\_Byte*** ( *Referenced BLOB* ; *Replace Byte Value* ; *Replacement Byte Value* )

***BLOB\_Replace\_Byte***

(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Replace Byte Value* : **Longint**  
    -> *Replacement Byte Value* : **Longint**  
)

| Parameter                     | Type    | Description                                      |
|-------------------------------|---------|--|
| <i>Referenced BLOB</i>        | Pointer | Referenced BLOB to perform byte replacement upon |
| <i>Replace Byte Value</i>     | Longint | ASCII value of bytes to replace                  |
| <i>Replacement Byte Value</i> | Longint | ASCII value of replacement bytes                 |

The method ***BLOB\_Replace\_Byte*** will perform a single byte replacement through the contents of a referenced BLOB.

*Referenced BLOB* is a pointer to a BLOB containing bytes to be scanned for replacement. The replacement is done directly within *Referenced BLOB*.

*Replace Byte Value* is the ASCII value of the bytes within *Referenced BLOB* which will be replaced.

*Replacement Byte Value* is the ASCII value of the bytes to be the replacement for all *Replace Byte Value* bytes in *Referenced BLOB*.

**Note:** the method ***BLOB\_Replace\_Byte*** was added in BASH v1.5.5.



## **BLOB\_Replace\_Text\_Case**

***BLOB\_Replace\_Text\_Case*** ( *Referenced BLOB* ; *Replace Text* ; *Replacement Text* ; *Beginning Offset* ; *Search Bytes* ) => *Replacement Count*

### ***BLOB\_Replace\_Text\_Case***

```
(
    -> Referenced BLOB : Pointer
    -> Replace Text : Text
    -> Replacement Text : Text
    -> Beginning Offset : Longint
    -> Search Bytes : Longint
)
=> Replacement Count : Longint
```

| Parameter | Type | Description |
|-----------|------|-------------|
|-----------|------|-------------|

|                          |                |   |
|--------------------------|----------------|---|
| <i>Referenced BLOB</i>   | <b>Pointer</b> | Referenced BLOB to perform byte replacement upon                            |
| <i>Replace Text</i>      | <b>Text</b>    | Text to be removed  |
| <i>Replacement Text</i>  | <b>Text</b>    | Text to be inserted   |
| <i>Beginning Offset</i>  | <b>Longint</b> | Offset within specified BLOB to beginning scanning for specified text value |
| <i>Search Bytes</i>      | <b>Longint</b> | Number of bytes to scan for specified text values                           |
| <i>Replacement Count</i> | <b>Longint</b> | Number of replacements done within specified BLOB                           |

The method ***BLOB\_Replace\_Text\_Case*** will perform a sequential, case sensitive replacement of a specified text value within a referenced BLOB.

The replacement is done sequentially from the specified beginning byte offset. It will continue sequential up to, but not past, the number of bytes specified.

*Referenced BLOB* is a pointer to a BLOB containing bytes to be scanned for replacement. The replacement is done directly within *Referenced BLOB*.

*Replace Text* is the text to search for within *Referenced BLOB*.

*Replacement Text* is the text value to replace the complete contents of every occurrence of *Replace Text* found within the specified byte range within *Referenced BLOB*. For each replacement operation, the size of the *Referenced BLOB* will be resized, as needed, to accommodate length differences between *Replace Text* and *Replacement Text*.

*Beginning Offset* is the byte offset within *Referenced BLOB* to begin the search for *Search Text*. If the search is to be done from the beginning of *Referenced BLOB*, pass zero (0) as the value for *Beginning Offset*.

*Search Bytes* is the number of bytes past *Beginning Offset* within *Referenced BLOB* which the value *Replace Text* should be searched for. The search will terminate after *Search Bytes* if no match is found. To search until

the end of *Referenced BLOB* , pass MaxLong as the value for *Search Bytes* .

**Note:** the method *BLOB\_Replace\_Text\_Case* was added in BASH v1.5.7.



## **BLOB\_Replace\_Text\_NonCase**

**BLOB\_Replace\_Text\_NonCase** ( *Referenced BLOB* ; *Replace Text* ;  
*Replacement Text* ; *Beginning Offset* ; *Search Bytes* ) =>  
*Replacement Count*

**BLOB\_Replace\_Text\_NonCase**  
(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Replace Text* : **Text**  
    -> *Replacement Text* : **Text**  
    -> *Beginning Offset* : **Longint**  
    -> *Search Bytes* : **Longint**  
)  
=> *Replacement Count* : **Longint**

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>  |
|--------------------------|----------------|---|
| <i>Referenced BLOB</i>   | <b>Pointer</b> | Referenced BLOB to perform byte replacement upon                            |
| <i>Replace Text</i>      | <b>Text</b>    | Text to be removed  |
| <i>Replacement Text</i>  | <b>Text</b>    | Text to be inserted   |
| <i>Beginning Offset</i>  | <b>Longint</b> | Offset within specified BLOB to beginning scanning for specified text value |
| <i>Search Bytes</i>      | <b>Longint</b> | Number of bytes to scan for specified text values                           |
| <i>Replacement Count</i> | <b>Longint</b> | Number of replacements done within specified BLOB                           |

The method *BLOB\_Replace\_Text\_NonCase* will perform a sequential, non-case sensitive replacement of a specified text value within a referenced BLOB.

The replacement is done sequentially from the specified beginning byte offset. It will continue sequential up to, but not past, the number of bytes specified.

*Referenced BLOB* is a pointer to a BLOB containing bytes to be scanned for replacement. The replacement is done directly within *Referenced BLOB* .

*Replace Text* is the text to search for within *Referenced BLOB* .

*Replacement Text* is the text value to replace the complete contents of every occurrence of *Replace Text* found within the specified byte range within *Referenced BLOB* . For each replacement operation, the size of the *Referenced BLOB* will be resized, as needed, to accommodate length differences between *Replace Text* and *Replacement Text* .

*Beginning Offset* is the byte offset within *Referenced BLOB* to begin the search for *Search Text* . If the search is to be done from the beginning of *Referenced BLOB* , pass zero (0) as the value for *Beginning Offset* .

*Search Bytes* is the number of bytes past *Beginning Offset* within *Referenced BLOB* which the value *Replace Text* should be searched for. The search will terminate after *Search Bytes* if no match is found. To search until the end of *Referenced BLOB* , pass MaxLong as the value for *Search Bytes* .

**Note:** the method *BLOB\_Replace\_Text\_NonCase* was added in BASH v1.5.7.



## **BLOB\_XOR\_Bytes**

**BLOB\_XOR\_Bytes** ( *Referenced Source BLOB* ; *Referenced Operand BLOB* ; *Referenced Result BLOB* )

**BLOB\_XOR\_Bytes**

(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Referenced Operand BLOB* : **Pointer**  
    -> *Referenced Result BLOB* : **Pointer**  
)

| <b>Parameter</b>               | <b>Type</b> | <b>Description</b>                              |
|--------------------------------|-------------|---|
| <i>Referenced BLOB</i>         | Pointer     | Referenced BLOB use to create XOR result BLOB   |
| <i>Referenced Operand BLOB</i> | Pointer     | Referenced BLOB use to create XOR result BLOB   |
| <i>Referenced Result BLOB</i>  | Pointer     | Referenced BLOB to contain resulting XORed BLOB |

The method ***BLOB\_XOR\_Bytes*** will perform a sequential XOR operation on every byte within two specified BLOBs and return the resulting XORed BLOB.

If the two source BLOBs, *Referenced Source BLOB* and *Referenced Operand BLOB* are of different size, then the resulting BLOB *Referenced Result BLOB* will be the size of the larger with padding bytes of the shorter source BLOB assumed to be NULL bytes.

*Referenced Source BLOB* and *Referenced Operand BLOB* are pointers to BLOBs which will have their contents XORed byte for byte.

*Referenced Result BLOB* will contain the byte for byte XORing of the contents of the two referenced source BLOBs.

**Note:** the method ***BLOB\_XOR\_Bytes*** was added in BASH v1.5.9.



# CODEC Module

The CODEC module provides basic encoding and decoding routines for many popular coding formats. Where applicable, encoding and decoding routines for both text and BLOB variable types have been included to handle all needs within 4th Dimension. With the exception of the variable types employed, encoding and decoding of text and BLOBs work exactly the same.

## CLE Encoding Scheme

The CLE (Carriage return, Linefeed, Equal) encoding scheme is merely a shortened version of the URL encoding scheme. It provides for for basic named value pair storage within a single text value. It is ideal for the storage of NVP values within a single text value in 4th Dimension. This makes it very easy to make human readable preferences files which are stored in the file system of the OS.

In essence, the CLE encoding scheme provides for the following translation of bytes:

| ASCII Value | ASCII Title     | Encoded |
|-------------|-----------------|---------|
| 13          | Carriage Return | &D      |
| 10          | Linefeed        | &A      |
| 61          | Equal Sign      | &3D     |

**Note:** the CODEC module was initially added in BASH v1.5.1.



## CODEC\_Decompile\_Base64\_x

**CODEC\_Decompile\_Base64\_x**( Base64 Encoded Text) => Decoded Text

**CODEC\_Decompile\_Base64\_x**

```
(  
    -> Base64 Encoded Text: Text  
)
```

=> *Decoded Text*: **Text**

| <b>Parameter</b>           | <b>Type</b> | <b>Description</b>                         |
|----------------------------|-------------|--|
| <i>Base64 Encoded Text</i> | <b>Text</b> | Base64 encoded text which is to be decoded |
| <i>Decoded Text</i>        | <b>Text</b> | Decoding of <i>Base64 Encoded Text</i>     |

The method ***CODEC\_Decode\_Base64\_x*** decodes a base64 encoded text value. Specifications for the base64 encoding scheme are available in RFC 2045, available at:

[http://www.deepskytech.com/rfcs/rfc\\_2045.txt](http://www.deepskytech.com/rfcs/rfc_2045.txt)

*Base64 Encoded Text* is the base64 encoded text which is to be decoded.

*Decoded Text* is *Base64 Encoded Text* decoded.

**Note:** the method ***CODEC\_Decode\_Base64\_x*** was added in BASH v1.5.1.



## **CODEC\_Decode\_Base64\_z**

***CODEC\_Decode\_Base64\_z***( *Referenced BLOB*)

***CODEC\_Decode\_Base64\_z***

(  
    -> *Referenced BLOB: Pointer*  
)

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>               |
|------------------------|----------------|----------------------------------|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Reference to base64 encoded BLOB |

The method ***CODEC\_Decode\_Base64\_z*** decodes a base64 encoded BLOB value. Specifications for the base64 encoding scheme are available in RFC 2045, available at:

[http://www.deepskytech.com/rfcs/rfc\\_2045.txt](http://www.deepskytech.com/rfcs/rfc_2045.txt)

*Referenced BLOB* is the referenced base64 encoded BLOB which is to be decoded. The decoded BLOB is returned directly in this referenced value.

**Note:** the method *CODEC\_Decode\_Base64\_z* was added in BASH v1.5.1.



## **CODEC\_Decode\_CLE\_x**

**CODEC\_Decode\_CLE\_x**( *CLE Encoded Text* ) => *Decoded Text*

**CODEC\_Decode\_CLE\_x**  
(  
    -> *CLE Encoded Text*: **Text**  
)  
=> *Decoded Text*: **Text**

| <b>Parameter</b>        | <b>Type</b> | <b>Description</b>                   |
|-------------------------|-------------|--------------------------------------|
| <i>CLE Encoded Text</i> | <b>Text</b> | CLE encoded text value to be decoded |
| <i>Decoded Text</i>     | <b>Text</b> | Decoding of <i>CLE Encoded Text</i>  |

The method *CODEC\_Decode\_CLE\_x* returns the decoding of a single CLE encoded value. Details on CLE encoding are available in the section entitled **CLE Encoding Scheme**, above.

*CLE Encoded Text* is a CLE encoded text value which is to be decoded.

*Decoded Text* is *CLE Encoded Text* decoded.

**Note:** the method *CODEC\_Decode\_CLE\_x* was added in BASH v1.5.1.



## **CODEC\_Decode\_Hex\_x**

**CODEC\_Decode\_Hex\_x** ( *Hex Encoded Text* ) => *Decoded ASCII Text*

**CODEC\_Decode\_Hex\_x**  
(  
    -> *Hex Encoded Text* : **Text**

)  
=> *Decoded ASCII Text* : Text

| Parameter                 | Type | Description                          |
|---------------------------|------|--------------------------------------|
| <i>Hex Encoded Text</i>   | Text | Hex encoded text value to be decoded |
| <i>Decoded ASCII Text</i> | Text | Hex decoded text value               |

The method *CODEC\_Decode\_Hex\_x* will hexadecimal decoded a specified text value and return the resulting decoded text value.

*Hex Encoded Text* is a text value containing a hexadecimal encoded text which is to be decoded.

*Decoded ASCII Text* is *Hex Encoded Text* hexadecimal decoded.

NOTE: remember that a hexadecimal decoded value occupies only half the number of bytes as its encoded value.

Note: the method *CODEC\_Decode\_Hex\_x* was added in BASH v1.5.8.

---

## **CODEC\_Decode\_Hex\_z**

*CODEC\_Decode\_Hex\_z* ( *Referenced BLOB* )

*CODEC\_Decode\_Hex\_z*  
(  
    -> *Referenced BLOB* : Pointer  
)

| Parameter              | Type    | Description  |
|------------------------|---------|--|
| <i>Referenced BLOB</i> | Pointer | Pointer to BLOB containing hexadecimal encoded value to be decoded |

The method *CODEC\_Decode\_Hex\_z* will hexadecimal decode the contents of a referenced BLOB.

*Referenced BLOB* is a pointer to a BLOB containing a hexadecimal encoded value. The decoded value will be returned in the same referenced BLOB.

NOTE: remember that a hexadecimal decoded value occupies only half the number of bytes as its encoded value.

**Note:** the method *CODEC\_Decode\_Hex\_z* was added in BASH v1.5.8.



## **CODEC\_Decode\_URL\_x**

**CODEC\_Decode\_URL\_x**( *URL Encoded Text*; *Translation Option* ) =>  
*Decoded Text*

**CODEC\_Decode\_URL\_x**  
(  
    -> *URL Encoded Text*: **Text**  
    -> *Translation Option*: **Longint**  
)  
=> *Decoded Text*: **Text**

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>   |
|---------------------------|----------------|--|
| <i>URL Encoded Text</i>   | <b>Text</b>    | URL encoded text value to be decoded                         |
| <i>Translation Option</i> | <b>Longint</b> | Translation option is qi for decoding "+" values into spaces |
| <i>Decoded Text</i>       | <b>Text</b>    | Decoding of <i>URL Encoded Text</i>                          |

The method *CODEC\_Decode\_URL\_x* returns the decoding of a single URL encoded value. Details on URL encoding are available in RFC 1738, available at:

[http://www.deepskytech.com/rfcs/rfc\\_1738.txt](http://www.deepskytech.com/rfcs/rfc_1738.txt)

*URL Encoded Text* is an URL encoded text value which is to be decoded.

*Translation Option* is option flag for how to decode plus ("+", ASCII value 43) values within *URL Encoded Text*. If *Translation Option* equals zero (0) then pluses are

translated into spaces (ASCII value 32). Otherwise, plusses will not be translated into spaces.

*Decoded Text* is *URL Encoded Text* decoded.

**Note:** the method *CODEC\_Decode\_URL\_x* was added in BASH v1.5.1.



## **CODEC\_Decode\_URL\_z**

**CODEC\_Decode\_URL\_z** ( *Referenced BLOB* ; *Translation Option* )

**CODEC\_Decode\_URL\_z**

(  
    -> *Referenced BLOB* : **Pointer**  
    -> *Translation Option* : **Longint**  
)

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>   |
|---------------------------|----------------|--|
| <i>Referenced BLOB</i>    | <b>Pointer</b> | Referenced BLOB to URL decode                                |
| <i>Translation Option</i> | <b>Longint</b> | Translation option is qi for decoding "+" values into spaces |

The method *CODEC\_Decode\_URL\_z* returns the decoding of a single URL encoded value. Details on URL encoding are available in RFC 1738, available at:

[http://www.deepskytech.com/rfcs/rfc\\_1738.txt](http://www.deepskytech.com/rfcs/rfc_1738.txt)

*Referenced BLOB* is a pointer to a BLOB containing URL encoded data which is to be decoded. The decoding is done directly within *Referenced BLOB* .

*Translation Option* is option flag for how to decode plus ("+", ASCII value 43) values within *Referenced BLOB* . If *Translation Option* equals zero (0) then pluses are translated into spaces (ASCII value 32). Otherwise, plusses will not be translated into spaces.

**Note:** the method *CODEC\_Decode\_URL\_z* was added in BASH v1.5.5.



## CODEC\_Decode\_UUEncode\_File

**CODEC\_Decode\_UUEncode\_File** ( *Referenced BLOB* ) => *File Name*

**CODEC\_Decode\_UUEncode\_File**

```
(  
    -> Referenced BLOB : Pointer  
)  
=> File Name : Text
```

| Parameter              | Type           | Description   |
|------------------------|----------------|---|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Pointer to BLOB containing UUEncoded file which is the be decoded |
| <i>File Name</i>       | <b>Text</b>    | File name of the original document                                |

The method **CODEC\_Decode\_UUEncode\_File** will decode a UUEncoded document referenced in a BLOB and return the original document name. Details on UUEncoding are available in the following document:

<http://www.deepskytech.com/rfcs/uuencode.txt>

*Referenced BLOB* is a pointer to a BLOB containing the UUEncoded document to be decoded.

*File Name* is the name of the original document which was UUEncoded.

**Note:** the method **CODEC\_Decode\_UUEncode\_File** was added in BASH v1.5.9.



## CODEC\_Decode\_UUEncode\_x

**CODEC\_Decode\_UUEncode\_x** ( *Encoded Text* ) => *Decoded Text*

**CODEC\_Decode\_UUEncode\_x**

```
(  
    -> Encoded Text : Text  
)  
=> Decoded Text : Text
```

| Parameter           | Type | Description                          |
|---------------------|------|--------------------------------------|
| <i>Encoded Text</i> | Text | UUEncoded text which will be decoded |
| <i>Decoded Text</i> | Text | UUDecoded text                       |

The method ***CODEC\_Decode\_UUEncode\_x*** will decode a UUEncoded text value and return the decoded text value. Details on UUEncoding are available in the following document:

<http://www.deepskytech.com/rfcs/uuencode.txt>

*Encoded Text* is a text value which has been UUEncoded. It will be decoded in this method.

*Decoded Text* is the decoding of *Encoded Text* using the UUEncoding coding schema.

**Note:** the method ***CODEC\_Decode\_UUEncode\_x*** was added in BASH v1.5.9.



## **CODEC\_Decode\_UUEncode\_z**

***CODEC\_Decode\_UUEncode\_z*** ( *Referenced BLOB* )

***CODEC\_Decode\_UUEncode\_z***  
 (  
     -> *Referenced BLOB* : **Pointer**  
 )

| Parameter              | Type    | Description  |
|------------------------|---------|--|
| <i>Referenced BLOB</i> | Pointer | Pointer to a BLOB containing UUEncoded data which is to be decoded |

The method ***CODEC\_Decode\_UUEncode\_z*** will decode previously UUEncoded data stored in a specified BLOB being referernced. Details on UUEncoding are available in the following document:

<http://www.deepskytech.com/rfcs/uuencode.txt>



*Referenced BLOB* is a pointer to a BLOB containing a UUEncoded encoded value. The decoded value will be returned in the same referenced BLOB.

**Note:** the method *CODEC\_Decompile\_UUEncode\_z* was added in BASH v1.5.9.



## **CODEC\_Encode\_Base64\_x**

**CODEC\_Encode\_Base64\_x**( *Text Value* ) => *Base64 Encoded Text*

**CODEC\_Encode\_Base64\_x**

```
(  
    -> Text Value: Text  
)  
=> Base64 Encoded Text: Text
```

| <b>Parameter</b>           | <b>Type</b> | <b>Description</b>                   |
|----------------------------|-------------|--------------------------------------|
| <i>Text Value</i>          | <b>Text</b> | Text value to be base64 encoded      |
| <i>Base64 Encoded Text</i> | <b>Text</b> | Base64 encoding of <i>Text Value</i> |

The method *CODEC\_Encode\_Base64\_x* base64 encodes a supplied text value. Specifications for the base64 encoding scheme are available in RFC 2045, available at:

[http://www.deepskytech.com/rfcs/rfc\\_2045.txt](http://www.deepskytech.com/rfcs/rfc_2045.txt)

*Text Value* is the text which is to be base64 encoded.

*Base64 Encoded Text* is *Text Value* base64 encoded.

**Note:** the method *CODEC\_Encode\_Base64\_x* was added in BASH v1.5.1.



## **CODEC\_Encode\_Base64\_z**

**CODEC\_Encode\_Base64\_z**( *Referenced BLOB* )

**CODEC\_Encode\_Base64\_z**

```
(
```

-> *Referenced BLOB: Pointer*  
)

| Parameter              | Type    | Description                            |
|------------------------|---------|--|
| <i>Referenced BLOB</i> | Pointer | Reference to BLOB to be base64 encoded |

The method ***CODEC\_Encode\_Base64\_z*** base64 encodes a referenced BLOB value. Specifications for the base64 encoding scheme are available in RFC 2045, available at:

[http://www.deepskytech.com/rfc/rfc\\_2045.txt](http://www.deepskytech.com/rfc/rfc_2045.txt)

*Referenced BLOB* is the referenced BLOB which is to be base64 encoded. The encoded BLOB is returned directly in this referenced value.

**Note:** the method ***CODEC\_Encode\_Base64\_z*** was added in BASH v1.5.1.



## **CODEC\_Encode\_CLE\_x**

***CODEC\_Encode\_CLE\_x***( *Text Value* ) => *CLE Encoded Text*

***CODEC\_Encode\_CLE\_x***

(  
    -> *Text Value: Text*  
)  
=> *CLE Encoded Text: Text*

| Parameter               | Type | Description                       |
|-------------------------|------|-----------------------------------|
| <i>Text Value</i>       | Text | Text value to be CLE encoded      |
| <i>CLE Encoded Text</i> | Text | CLE encoding of <i>Text Value</i> |

The method ***CODEC\_Encode\_CLE\_x*** returns a supplied text value CLE encoded. Details on CLE encoding are available in the section entitled **CLE Encoding Scheme**, above.

*Text Value* is the text value to be

*CLE Encoded Text* is *Text Value* CLE encoded.

**Note:** the method *CODEC\_Encode\_CLE\_x* was added in BASH v1.5.1.



## **CODEC\_Encode\_CRAMMD5\_z**

**CODEC\_Encode\_CRAMMD5\_z** ( *Username* ; *Key* ; *Referenced Source BLOB* ; *Referenced Result BLOB* )

**CODEC\_Encode\_CRAMMD5\_z**  
(  
    -> *Username* : **Text**  
    -> *Key* : **Text**  
    -> *Referenced Source BLOB* : **Pointer**  
    -> *Referenced Result BLOB* : **Pointer**  
)

| <b>Parameter</b>              | <b>Type</b>    | <b>Description</b>  |
|-------------------------------|----------------|---|
| <i>Username</i>               | <b>Text</b>    | Username to use in creating CRAM MD5 encoding                             |
| <i>Key</i>                    | <b>Text</b>    | Key to use in creating CRAM MD5 encoding                                  |
| <i>Referenced Source BLOB</i> | <b>Pointer</b> | Pointer to BLOB containing challenge to use in creating CRAM MD5 encoding |
| <i>Referenced Result BLOB</i> | <b>Pointer</b> | Pointer to BLOB to contain CRAM MD5 encoding                              |

The method *CODEC\_Encode\_CRAMMD5\_z* will create a properly formatted CRAM MD5 digest from the parameter values supplied. Specifications for the CRAM MD5 encoding scheme are available in RFC 2195, available at:

[http://www.deepskytech.com/rfcs/rfc\\_2195.txt](http://www.deepskytech.com/rfcs/rfc_2195.txt)

*Username* is the username to be used to create the CRAM MD5 encoding.

*Key* is the key to be used to create the CRAM MD5 encoding.

*Referenced Source BLOB* is a pointer to a BLOB container the challenge value which is to be used to create the CRAM MD5 encoding.

*Referenced Result BLOB* is a pointer to a BLOB which will contain the CRAM MD5 encoded value.

**Note:** the method *CODEC\_Encode\_CRAMMD5\_z* was added in BASH v1.5.9.



## **CODEC\_Encode\_Hex\_x**

**CODEC\_Encode\_Hex\_x** ( *ASCII Text to Encode* ) => *Hex Encoded Text*

**CODEC\_Encode\_Hex\_x**

(  
    -> *ASCII Text to Encode* : **Text**  
)  
    => *Hex Encoded Text* : **Text**

| <b>Parameter</b>            | <b>Type</b> | <b>Description</b>           |
|-----------------------------|-------------|------------------------------|
| <i>ASCII Text to Encode</i> | <b>Text</b> | Text value to be hex encoded |
| <i>Hex Encoded Text</i>     | <b>Text</b> | Hex encoded text value       |

The method *CODEC\_Encode\_Hex\_x* will hexadecimal encoded a specified text value and return the resulting encoded text value.

*ASCII Text to Encode* is a text value to be encoded.

*Hex Encoded Text* is *ASCII Text to Encode* hexadecimal encoded.

NOTE: remember that a hexadecimal encoded value occupies only twice the number of bytes as its decoded value.

**Note:** the method *CODEC\_Encode\_Hex\_x* was added in BASH v1.5.8.



## **CODEC\_Encode\_Hex\_z**

**CODEC\_Encode\_Hex\_z** ( *Referenced BLOB* )

## **CODEC\_Encode\_Hex\_z**

```
(  
    -> Referenced BLOB : Pointer  
)
```

| Parameter              | Type    | Description  |
|------------------------|---------|--|
| <i>Referenced BLOB</i> | Pointer | Pointer to BLOB containing value to be hexadecimal encoded |

The method *CODEC\_Encode\_Hex\_z* will hexadecimal encode the contents of a referenced BLOB.

*Referenced BLOB* is a pointer to a BLOB containing a value to be hexadecimal encoded. The encoded value will be returned in the same referenced BLOB.

NOTE: remember that a hexadecimal encoded value occupies only twice the number of bytes as its decoded value.

Note: the method *CODEC\_Encode\_Hex\_z* was added in BASH v1.5.8.



## **CODEC\_Encode\_KeyedMD5\_z**

**CODEC\_Encode\_KeyedMD5\_z** ( *Key* ; *Referenced Source BLOB* ; *Referenced Result BLOB* )

### **CODEC\_Encode\_KeyedMD5\_z**

```
(  
    -> Key : Text  
    -> Referenced Source BLOB : Pointer  
    -> Referenced Result BLOB : Pointer  
)
```

| Parameter                     | Type    | Description  |
|-------------------------------|---------|--|
| <i>Key</i>                    | Text    | Key to use in creating Keyed MD5 encoding                                  |
| <i>Referenced Source BLOB</i> | Pointer | Pointer to BLOB containing challenge to use in creating Keyed MD5 encoding |

|                                   |                |  |
|-----------------------------------|----------------|--|
| <i>Referenced<br/>Result BLOB</i> | <b>Pointer</b> | <b>Pointer to BLOB to contain Keyed<br/>MD5 encoding</b> |
|-----------------------------------|----------------|--|

The method *CODEC\_Encode\_KeyedMD5\_z* will create a properly formatted Keyed MD5 digest (i.e. Keyed Hash) from the parameter values supplied. Specifications for the Keyed MD5 encoding scheme are available in RFC 2104, available at:

[http://www.deepskytech.com/rfcs/rfc\\_2104.txt](http://www.deepskytech.com/rfcs/rfc_2104.txt)

*Key* is the key to be used to create the Keyed MD5 encoding.

*Referenced Source BLOB* is a pointer to a BLOB container the challenge value which is to be used to create the Keyed MD5 encoding.

*Referenced Result BLOB* is a pointer to a BLOB which will contain the Keyed MD5 encoded value.

**Note:** the method *CODEC\_Encode\_KeyedMD5\_z* was added in BASH v1.5.9.



## **CODEC\_Encode\_MD5\_x**

*CODEC\_Encode\_MD5\_x* (Text Value ) => MD5 Encoded Text Digest

**CODEC\_Encode\_MD5\_x**

```
(
    -> Text Value : Text
)
=> MD5 Encoded Text Digest : Text
```

| <b>Parameter</b>           | <b>Type</b> | <b>Description</b>                  |
|----------------------------|-------------|-------------------------------------|
| Text Value                 | Text        | Text value to create MD5 digest for |
| MD5 Encoded<br>Text Digest | Text        | MD5 encoded digest of Text Value    |

The method *CODEC\_Encode\_MD5\_x* creates a MD5 encoded digest of a supplied text value. Specifications for the MD5 encoded digest scheme are available in RFC 1321, available at:

[http://www.deepskytech.com/rfcs/rfc\\_1321.txt](http://www.deepskytech.com/rfcs/rfc_1321.txt)

*Text Value* is the text which is to used to create the MD5 encoded digest.

*MD5 Encoded Text Value* is the MD5 encoded digest created using *Text Value* .

**Note:** the MD5 encoded digest is a one-way encoding schema. There is no way to retrieve the original value from an MD5 encoded digest. Often, MD5 encoded digests are used for logging into POP3 email servers when using the optional APOP authentication option.

**Note:** the method *CODEC\_Encode\_MD5\_x* was added in BASH v1.5.4.



## **CODEC\_Encode\_MD5\_z**

**CODEC\_Encode\_MD5\_z** ( *Referenced BLOB* )

**CODEC\_Encode\_MD5\_z**

(  
    -> *Referenced BLOB* : **Pointer**  
)

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>                                |
|------------------------|----------------|---|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Reference to BLOB value to encode into MD5 digest |

The method *CODEC\_Encode\_MD5\_z* creates a MD5 encoded digest from a referenced BLOB value. Specifications for the MD5 encoded digest scheme are available in RFC 1321, available at:

[http://www.deepskytech.com/rfcs/rfc\\_1321.txt](http://www.deepskytech.com/rfcs/rfc_1321.txt)

*Referenced BLOB* is the referenced BLOB to be used to create the MD5 encoded digest. The MD5 encoded digest is returned directly in this referenced value.

Note: the method *CODEC\_Encode\_MD5\_z* was added in BASH v1.5.4.



## **CODEC\_Encode\_URL\_x**

**CODEC\_Encode\_URL\_x**( *Text Value* ) => *URL Encoded Text*

**CODEC\_Encode\_URL\_x**

```
(  
    -> Text Value: Text  
)  
=> URL Encoded Text: Text
```

| Parameter               | Type        | Description                       |
|-------------------------|-------------|-----------------------------------|
| <i>Text Value</i>       | <b>Text</b> | Text value to be URL encoded      |
| <i>URL Encoded Text</i> | <b>Text</b> | URL encoding of <i>Text Value</i> |

The method *CODEC\_Encode\_URL\_x* returns a single text value URL encoded. Details on URL encoding are available in RFC 1738, available at:

[http://www.deepskytech.com/rfcs/rfc\\_1738.txt](http://www.deepskytech.com/rfcs/rfc_1738.txt)

The exact listing of ASCII byte values which are allowable can be modified. This listing is contained within the 'STR#' resource, ID 29821, entitled "Allowable ASCII Values for URLs" within the Affix BASH document. The values in this resource can be modified, as desired. Any ASCII values which are not contained in this resource will be URL encoded by this method.

*Text Value* is the text to be URL encoded.

*URL Encoded Text* is *Text Value* URL encoded.

Note: the method *CODEC\_Encode\_URL\_x* was added in BASH v1.5.1.

Note: as of BASH v1.5.3, the listing of allowable ASCII byte values was moved to the Affix BASH document.



Previous to this version, the allowable ASCII byte values list was stored in the resource fork of the structure file.



## **CODEC\_Encode\_URL\_z**

**CODEC\_Encode\_URL\_z** ( *Referenced BLOB* )

**CODEC\_Encode\_URL\_z**

(  
    -> *Referenced BLOB* : **Pointer**  
)

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>            |
|------------------------|----------------|-------------------------------|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Referenced BLOB to URL encode |

The method **CODEC\_Encode\_URL\_z** returns a single referenced value URL encoded. Details on URL encoding are available in RFC 1738, available at:

[http://www.deepskytech.com/rfcs/rfc\\_1738.txt](http://www.deepskytech.com/rfcs/rfc_1738.txt)

The exact listing of ASCII byte values which are allowable can be modified. This listing is contained within the 'STR#' resource, ID 29821, entitled "Allowable ASCII Values for URLs" within the Affix BASH document. The values in this resource can be modified, as desired. Any ASCII values which are not contained in this resource will be URL encoded by this method.

*Referenced BLOB* is a pointer to a BLOB containing the data to be URL encoded. The encoding is done directly within *Referenced BLOB*.

**Note:** the method **CODEC\_Encode\_URL\_z** was added in BASH v1.5.5.



## **CODEC\_Encode\_UUEncode\_File**

**CODEC\_Encode\_UUEncode\_File** ( *Referenced BLOB* ; *File Name* )

**CODEC\_Encode\_UUEncode\_File**

```
(
    -> Referenced BLOB : Pointer
    -> File Name : Text
)
```

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>  |
|------------------------|----------------|---|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Pointer to BLOB containing file which is the be UUEncoded |
| <i>File Name</i>       | <b>Text</b>    | File name of the document being UUEncoded                 |

The method *CODEC\_Encode\_UUEncode\_File* will encode a document referenced in a BLOB using the UUEncoded coding schema. Details on UUEncoding are available in the following document:

<http://www.deepskytech.com/rfcs/uuencode.txt>

*Referenced BLOB* is a pointer to a BLOB containing the document to be UUEncoded.

*File Name* is the name of the document which is to be UUEncoded.

**Note:** the method *CODEC\_Encode\_UUEncode\_File* was added in BASH v1.5.9.



## **CODEC\_Encode\_UUEncode\_x**

**CODEC\_Encode\_UUEncode\_x** ( *Text to Encode* ) => *Encoded Text*

**CODEC\_Encode\_UUEncode\_x**

```
(
    -> Text to Encode : Text
)
=> Encoded Text : Text
```

| <b>Parameter</b>      | <b>Type</b> | <b>Description</b>         |
|-----------------------|-------------|----------------------------|
| <i>Text to Encode</i> | <b>Text</b> | Text value to be UUEncoded |
| <i>Encoded Text</i>   | <b>Text</b> | UUEncoded text value       |

The method **CODEC\_Encode\_UUEncode\_x** will encode a text value using the UUEncode coding schema and return the encoded text value. Details on UUEncoding are available in the following document:

<http://www.deepskytech.com/rfcs/uuencode.txt>

*Text to Encode* is a text value to be encoded using the UUEncode coding schema in this method.

*Encoded Text* is the encoding of *Text to Encode* using the UUEncoding coding schema.

**Note:** the method **CODEC\_Encode\_UUEncode\_x** was added in BASH v1.5.9.



## **CODEC\_Encode\_UUEncode\_z**

**CODEC\_Encode\_UUEncode\_z** ( *Referenced BLOB* )

**CODEC\_Encode\_UUEncode\_z**

(  
    -> *Referenced BLOB* : **Pointer**  
)

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>                        |
|------------------------|----------------|---|
| <i>Referenced BLOB</i> | <b>Pointer</b> | Pointer to a BLOB which will be UUEncoded |

The method **CODEC\_Encode\_UUEncode\_z** will encode the contents of a specified referenced BLOB using the UUEncode coding schema. Details on UUEncoding are available in the following document:

<http://www.deepskytech.com/rfcs/uuencode.txt>

*Referenced BLOB* is a pointer to a BLOB which will be UUEncoded.

**Note:** the method **CODEC\_Encode\_UUEncode\_z** was added in BASH v1.5.9.



---

## CODEC\_ERROR

**CODEC\_ERROR** (*BASH Error Number*; *Special Error Text*; *Calling Method Name*)

### CODEC\_ERROR

```
(  
    -> BASH Error Number: Longint  
    -> Special Error Text: Text  
    -> Calling Method Name: Text  
)
```

| Parameter                  | Type    | Description   |
|----------------------------|---------|---|
| <i>BASH Error Number</i>   | Longint | Internal BASH error number                              |
| <i>Special Error Text</i>  | Text    | Special text to describe the exact error instance       |
| <i>Calling Method Name</i> | Text    | Name of the method that the error condition occurred in |

The method **CODEC\_ERROR** acts as a callback method from within the CODEC module for errors that may occur. Any time an error condition is detected within the CODEC module, a call to the method **CODEC\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the ARR method which call the **CODEC\_ERROR** method.

The **CODEC\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.

**Note:** the method **CODEC\_ERROR** was added in BASH v1.5.4.

## CONV Module

The CONV module handles conversions between different data types available within 4th Dimension. The CONV module also handle conversions between particularly common auxiliary formats which are commonly employed in 4th Dimension, including dotted IP addresses, single byte hexadecimal values (Hex2), four byte hexadecimal values (Hex8), ASCII values, etc.

### Hex2 and Hex8 Values

Hex2 and Hex8 values are representations of ASCII values, integers, longints, and text within hexadecimal notation. The Hex2 and Hex8 values are text values which contain the hexadecimal equivalent of converted bytes.

Hex2 values are text of length two bytes which represent a single byte value in hexadecimal. For instance, the following conversion table lists example ASCII value and their equivalent Hex2 values:

| <u>ASCII Value</u> | <u>Hex2 Value</u> |
|--------------------|-------------------|
| 10                 | 0A                |
| 13                 | 0D                |
| 27                 | 1B                |
| 32                 | 20                |
| 61                 | 3D                |
| 63                 | 3F                |
| 64                 | 40                |

**Note:** Hex2 values are *always* two bytes in length. This is true even for Hex2 values which when translated to decimal would be less than 16. Also, Hex2 values never have the commonly used ampersand ("&") at the beginning to indicate that the value is representing hexadecimal digits.

Hex8 values are text of length eight bytes which represent four byte values in hexadecimal. For instance,

the following conversion table lists example ASCII values and their equivalent Hex8 values:

| <u>ASCII Value</u> | <u>Hex8 Value</u> |
|--------------------|-------------------|
| 65, 115, 115, 13   | 4073730D          |
| 13, 27, 13, 27     | 0D1B0D1B          |
| 13, 10, 13, 10     | 0D0A0D0A          |

**Note:** Hex8 values are *always* eight bytes in length. Also, Hex8 values never have the commonly used ampersand ("&") at the beginning to indicate that the value is representing hexadecimal digits.

## Type Values

A Type value is text of length four (4) which represents a four (4) byte coercion of a Macintosh Type code. A Macintosh Type code is any four (4) byte data structure used as a key or attribute indicator. Commonly, Type values are known, depending on their usage, as Macintosh creator codes, Macintosh file type codes, resource types, and much more.

Technically, these values as they exist in 4th Dimension should be handled as longints. But, in many instances, 4th Dimension provides access only to the Type values as coerced textual equivalents. The CONV methods which deal with Type values allow for the easy conversion between standard 4D longint values and their equivalent values as coerced to and from text for use in 4th Dimension.

It is highly recommended that such type values, when stored within 4th Dimension, be handled exclusively as longints. Conversion to and from text values should be done immediately surrounding native calls to 4th Dimension commands. The importance of this matter is exemplified by the fact that resources of type 'TEXT' and 'text' are very different. But, when comparing their textual type values in 4th Dimension, they will be

considered equivalent. This can lead to no end of hassles and confusion when working in 4th Dimension.

**Note:** all BASH methods, in all modules of contained within the BASH component, deal with type values as longints, not coerced text. This includes all resource handling, file typing, etc., throughout the component. The advantages of using this format are obvious.

### Dotted IP Values

Dotted IP values are an alternate representation of a 32 bit (4 byte) values. A Dotted IP address will always have the format:

a.b.c.d

where a, b, c, and d are all values between 0 and 255, inclusive.

A common four (4) byte value in 4th Dimension is the longint variable type. So, it is a simple matter to store Dotted IP addresses within longint variables in 4th Dimension. By doing this, the storage is much more compact, manipulation is much easier, and operations perform much more quickly.

**Note:** the storage of dotted IP addresses within 4th Dimension as longints is not as straightforward as it may initially seem. For instance, a common operation to calculate for dotted IP addresses is to determine if a particular dotted IP address falls within a specified range of IP addresses (or matches a particular mask). Using integer comparison on the Dotted IP values as stored in longints would not yield consistent results for such an operation. Instead, bit arithmetic must be used on the Dotted IP values stored in longints. This is not a complexity or limitation of the storing Dotted IP values in longints. Rather, the code for such comparisons is actually much more efficient and not as prone to silly textual and typing errors.

**Note:** the CONV module was initially added in BASH v1.5.1.

---

## **CONV\_ASCII\_to\_Hex2**

**CONV\_ASCII\_to\_Hex2** ( *ASCII Value* ) => *Hex2 Value*

**CONV\_ASCII\_to\_Hex2**

```
(  
    -> ASCII Value: Longint  
)  
    => Hex2 Value: String2
```

| Parameter          | Type    | Description                           |
|--------------------|---------|---------------------------------------|
| <i>ASCII Value</i> | Longint | ASCII value of a single byte          |
| <i>Hex2 Value</i>  | String2 | Hex2 equivalent of <i>ASCII Value</i> |

The method **CONV\_ASCII\_to\_Hex2** will convert a single, integral byte value into its Hex2 equivalent.

*ASCII Value* is a single ASCII byte value, a number between 0 and 255 (inclusive). If *ASCII Value* is outside the accepted range of valid values, only the lower eight (8) bits) will be used to calculate the converted return value.

*Hex2 Value* is *ASCII Value* represented in hexadecimal. *Hex2 Value* will always be two bytes in length.

**Note:** the method **CONV\_ASCII\_to\_Hex2** was added in BASH v1.5.1.

---

## **CONV\_ASCII\_to\_PrintableText**

**CONV\_ASCII\_to\_PrintableText**( *ASCII Value* ) => *Printable Character*

**CONV\_ASCII\_to\_PrintableText**

```
(
```



-> *ASCII Value*: **Longint**  
)  
=> *Printable Character*: **Text**

| Parameter                  | Type           | Description                             |
|----------------------------|----------------|---|
| <i>ASCII Value</i>         | <b>Longint</b> | ASCII value of a single byte            |
| <i>Printable Character</i> | <b>Text</b>    | Printable version of <i>ASCII Value</i> |

The method *CONV\_ASCII\_to\_PrintableText* will convert a single ASCII value into the textual equivalent which is printable. ASCII values which are non-printable are converted to a period (".") for display and printing.

The range of directly printable ASCII values varies depending on the platform. On Macintosh, the range of printable ASCII values is from 32 to 255, inclusive. On Windows, the range is reduced to 32 to 126, inclusive. All ASCII values which are considered non-printable on the current platform will be converted to periods (".") for display and printing.

*ASCII Value* is the integral ASCII value to be converting to text for display and/or printing. All values of *ASCII Value* which are outside the range of acceptable ASCII values (0 to 255, inclusive) will be translated to periods (".").

*Printable Character* is the textual equivalent of *ASCII Value* which is directly printable.

**Note:** the method *CONV\_ASCII\_to\_PrintableText* was added in BASH v1.5.1.



## **CONV\_Coerce\_from\_Text**

**CONV\_Coerce\_from\_Text**( *Text Value*; *Reference to Coerced Text*)

**CONV\_Coerce\_from\_Text**

(  
-> *Text Value*: **Text**  
-> *Reference to Coerced Text*: **Pointer**

)

| Parameter                        | Type    | Description   |
|----------------------------------|---------|---|
| <i>Text Value</i>                | Text    | Text value to coerce                                |
| <i>Reference to Coerced Text</i> | Pointer | Reference to variable to contain coerced text value |

The method *CONV\_Coerce\_from\_Text* will coerce a text value into a referenced variable of most any type. Coercion is done blindly on the text value, as it is merely forced into the referenced value (the only exception is that for referenced data variables, in which case the data value is normalized).

*Text Value* is the text value which is going to be coerced.

*Reference to Coerced Text* is a pointer to a variable which will contain the coerced *Text Value*. This referenced variable can be a field or variable of type boolean, date, integer, longint, real, string, text, or time.

**Note:** the method *CONV\_Coerce\_from\_Text* was added in BASH v1.5.1.



## CONV\_Coerce\_to\_Text

*CONV\_Coerce\_to\_Text*(*Referenced Value*) => *Coerced Text*

*CONV\_Coerce\_to\_Text*  
(  
    -> *Referenced Value*: **Pointer**  
)  
=> *Coerced Text*: **Text**

| Parameter               | Type    | Description   |
|-------------------------|---------|---|
| <i>Referenced Value</i> | Pointer | Pointer to value to coerce into text                          |
| <i>Coerced Text</i>     | Text    | Textually coerced value referenced by <i>Referenced Value</i> |

The method *CONV\_Coerce\_to\_Text* will coerce a referenced value of most any type to text. Coercion is

done blindly to the textual equivalent, as it is merely forced from the referenced value.

*Reference Value* is a pointer to a variable which contains the value to coerce to text. This referenced variable can be a field or variable of type boolean, date, integer, longint, real, string, text, or time.

*Coerced Text* contains the coerced value referenced by *Reference Value*.

**Note:** the method *CONV\_Coerce\_to\_Text* was added in BASH v1.5.1.



## CONV\_ERROR

**CONV\_ERROR** ( *BASH Error Number*; *Special Error Text*; *Calling Method Name* )

### CONV\_ERROR

(  
-> *BASH Error Number*: Longint  
-> *Special Error Text*: Text  
-> *Calling Method Name*: Text  
)

| Parameter                  | Type    | Description   |
|----------------------------|---------|---|
| <i>BASH Error Number</i>   | Longint | Internal BASH error number                              |
| <i>Special Error Text</i>  | Text    | Special text to describe the exact error instance       |
| <i>Calling Method Name</i> | Text    | Name of the method that the error condition occurred in |

The method *CONV\_ERROR* acts as a callback method from within the CONV module for errors that may occur. Any time an error condition is detected within the CONV module, a call to the method *CONV\_ERROR* is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the

*Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the DSS method which call the **CONV\_ERROR** method.

The **CONV\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.

**Note:** the method **CONV\_ERROR** was added in BASH v1.5.1.



## **CONV\_Hex8\_to\_Longint**

**CONV\_Hex8\_to\_Longint**(*Hex8 Value*) => *Longint Value*

**CONV\_Hex8\_to\_Longint**

(  
    -> *Hex8 Value*: Text  
)  
    => *Longint Value*: Longint

| Parameter            | Type    | Description                             |
|----------------------|---------|---|
| <i>Hex8 Value</i>    | Text    | Hex8 value to convert to longint        |
| <i>Longint Value</i> | Longint | Longint conversion of <i>Hex8 Value</i> |

The method **CONV\_Hex8\_to\_Longint** converts a Hex8 value to longint.

*Hex8 Value* is the Hex8 value to convert to longint. If the length of *Hex8 Value* is greater than eight (8) bytes, then only the first eight bytes are used to create the longint conversion.

*Longint Value* is the conversion of the first eight bytes of *Hex8 Value*.

**Note:** the method **CONV\_Hex8\_to\_Longint** was added in BASH v1.5.1.



## CONV\_Hex8\_to\_Text

**CONV\_Hex8\_to\_Longint**( *Hex8 Value*) => *Text Value*

**CONV\_Hex8\_to\_Longint**

```
(  
    -> Hex8 Value: Text  
)  
=> Text Value: Text
```

| Parameter         | Type | Description                             |
|-------------------|------|---|
| <i>Hex8 Value</i> | Text | Hex8 value to convert to text           |
| <i>Text Value</i> | Text | Textual conversion of <i>Hex8 Value</i> |

The method **CONV\_Hex8\_to\_Text** converts a Hex8 value to text.

*Hex8 Value* is the Hex8 value to convert to text. If the length of *Hex8 Value* is greater than eight (8) bytes, then only the first eight bytes are used to create the text conversion.

*Text Value* is the conversion of the first eight bytes of *Hex8 Value*. *Text Value* will always be four (4) bytes in length. The conversion to text is done blindly, without respecting printable ASCII values or even invalid ASCII values within a 4th Dimension text variable (i.e. ASCII value 0 is not a good value to set into a text variable in 4D).

**Note:** the method **CONV\_Hex8\_to\_Text** was added in BASH v1.5.1.



## CONV\_IP\_to\_Longint

**CONV\_IP\_to\_Longint**( *Dotted IP Address*) => *Longint Value*

**CONV\_IP\_to\_Longint**

```
(  
    -> Dotted IP Address: Text  
)
```

=> *Longint Value: Longint*

| Parameter                | Type    | Description                                    |
|--------------------------|---------|--|
| <i>Dotted IP Address</i> | Text    | Dotted IP address value to convert to longint  |
| <i>Longint Value</i>     | Longint | Longint conversion of <i>Dotted IP Address</i> |

The method *CONV\_IP\_to\_Longint* converts a Dotted IP value to longint.

*Dotted IP Address* is the text value of the dotted IP address to convert to longint. It must be a complete and well formed dotted IP address value in text. The conversion is done blindly once the complete and well formed nature of *Dotted IP Address* is determined.

*Longint Value* is the conversion of *Dotted IP Address* to a longint value.

**Note:** the method *CONV\_IP\_to\_Longint* was added in BASH v1.5.1.



## **CONV\_Longint\_to\_Hex8**

*CONV\_Longint\_to\_Hex8*(*Longint Value*) => *Hex8 Value*

***CONV\_Longint\_to\_Hex8***

(  
    -> *Longint Value: Longint*  
)  
=> *Hex8 Value: Text*

| Parameter            | Type    | Description                             |
|----------------------|---------|---|
| <i>Longint Value</i> | Longint | Longint value to convert to Hex8        |
| <i>Hex8 Value</i>    | Text    | Hex8 conversion of <i>Longint Value</i> |

The method *CONV\_Longint\_to\_Hex8* converts a longint value to Hex8.

*Longint Value* is the longint value to convert to Hex8.

*Hex8 Value* is the conversion of *Longint Value* to Hex8. *Hex8 Value* will always be eight (8) bytes in length.

**Note:** the method *CONV\_Longint\_to\_Hex8* was added in BASH v1.5.1.



## **CONV\_Longint\_to\_IP**

**CONV\_Longint\_to\_IP**( *Longint Value* ) => *Dotted IP Address*

**CONV\_Longint\_to\_IP**

(  
    -> *Longint Value*: Longint  
)  
    => *Dotted IP Address*: Text

| Parameter                | Type    | Description                                  |
|--------------------------|---------|--|
| <i>Longint Value</i>     | Longint | Longint value to covert to a Dotted IP value |
| <i>Dotted IP Address</i> | Text    | Dotted IP conversion of <i>Longint Value</i> |

The method *CONV\_Longint\_to\_IP* converts a longint to a complete and well form Dotted IP value.

*Longint Value* is the longint value to convert to a well formed and complete Dotted IP value.

*Dotted IP Address* is the text value of the dotted IP address converted from *Longint Value*. It will always be a complete and well formed dotted IP address value in text.

**Note:** the method *CONV\_Longint\_to\_IP* was added in BASH v1.5.1.



## **CONV\_Longint\_to\_Type**

**CONV\_Longint\_to\_Type**( *Longint Value* ) => *Type Value*

**CONV\_Longint\_to\_Type**

```
(
    -> Longint Value: Longint
)
=> Type Value: String4
```

| Parameter            | Type    | Description                             |
|----------------------|---------|---|
| <i>Longint Value</i> | Longint | Longint value to covert to a Type value |
| <i>Type Value</i>    | String4 | Type conversion of <i>Longint Value</i> |

The method **CONV\_Longint\_to\_Type** converts a longint to a valid Type value in text.

*Longint Value* is the longint value to convert to a textual Type value.

*Type Value* is the text value of the Type converted from *Longint Value*. *Type Value* will always be four (4) bytes in length. The conversion to text is done blindly, without respecting printable ASCII values or even invalid ASCII values within a 4th Dimension text variable (i.e. ASCII value 0 is not a good value to set into a text variable in 4D).

**Note:** the method **CONV\_Longint\_to\_Type** was added in BASH v1.5.1.



## CONV\_Text\_to\_Hex8

**CONV\_Text\_to\_Hex8**(*Text Value*) => *Hex8 Value*

**CONV\_Text\_to\_Hex8**

```
(
    -> Text Value: Text
)
=> Hex8 Value: Text
```

| Parameter         | Type | Description                          |
|-------------------|------|--------------------------------------|
| <i>Text Value</i> | Text | Text value to convert to Hex8        |
| <i>Hex8 Value</i> | Text | Hex8 conversion of <i>Text Value</i> |

The method **CONV\_Text\_to\_Hex8** converts a text value to Hex8.



*Text Value* is the text to convert to a Hex8 value. If *Text Value* is longer than four (4) bytes, then only the first four (4) bytes are used to create the resulting Hex8 value.

*Hex8 Value* is converted first four (4) bytes of *Text Value*. *Hex8 Value* will always be eight (8) bytes in length.

**Note:** the method *CONV\_Text\_to\_Hex8* was added in BASH v1.5.1.



## **CONV\_Text\_to\_Longint**

**CONV\_Text\_to\_Longint**( *Text Value* ) => *Longint Value*

**CONV\_Text\_to\_Longint**

(  
    -> *Text Value*: Text  
)  
    => *Longint Value*: Longint

| Parameter            | Type    | Description                             |
|----------------------|---------|---|
| <i>Text Value</i>    | Text    | Text value to convert to longint        |
| <i>Longint Value</i> | Longint | Longint conversion of <i>Text Value</i> |

The method *CONV\_Text\_to\_Longint* converts a text value to longint. It is functionally equivalent to using the native **Int** and **Num** commands in 4th Dimension.

*Text Value* is the text value to be converted to longint.

*Longint Value* is the converted *Text Value*.

**Note:** the method *CONV\_Text\_to\_Longint* was added in BASH v1.5.1.



## **CONV\_Text\_to\_Real**

**CONV\_Text\_to\_Real**( *Text Value* ) => *Real Value*

## **CONV\_Text\_to\_Real**

```
(  
    -> Text Value: Text  
)  
=> Real Value: Real
```

| Parameter  | Type | Description                   |
|------------|------|-------------------------------|
| Text Value | Text | Text value to convert to real |
| Real Value | Real | Real conversion of Text Value |

The method *CONV\_Text\_to\_Real* converts a text value to real. It is functionally equivalent to using the native **Num** command in 4th Dimension.

*Text Value* is the text value to be converted to real.

*Real Value* is the converted *Text Value*.

**Note:** the method *CONV\_Text\_to\_Real* was added in BASH v1.5.1.



## **CONV\_Type\_to\_Longint**

**CONV\_Type\_to\_Longint**(Type Value) => Longint Value

```
CONV_Type_to_Longint  
(  
    -> Type Value: String4  
)  
=> Longint Value: Longint
```

| Parameter     | Type    | Description                      |
|---------------|---------|----------------------------------|
| Type Value    | String4 | Type value to convert to longint |
| Longint Value | Longint | Longint conversion of Type Value |

The method *CONV\_Type\_to\_Longint* converts a valid Type value in text to longint.

*Type Value* is a valid Type value to convert to longint.

*Longint Value* is the longint value of the Type converted from *Type Value*.

**Note:** the method *CONV\_Type\_to\_Longint* was added in BASH v1.5.1.

# CRYPT Module

The CRYPT module provides basic encryption and decryption routines directly in 4th Dimension. With the first release of the CRYPT module, implementation of TEA is the sole purpose. With future releases of the BASH component, other encryption algorithms may be added.

## Tiny Encryption Algorithm (TEA)

The Tiny Encryption Algorithm is one of the fastest and most efficient cryptographic algorithms in existence. It was developed by David Wheeler and Roger Needham at the Computer Laboratory of Cambridge University. It is a Feistel cipher which uses operations from mixed (orthogonal) algebraic groups - XORs and additions in this case. It encrypts 64 data bits at a time using a 128-bit key. It seems highly resistant to differential cryptanalysis, and achieves complete diffusion (where a one bit difference in the plaintext will cause approximately 32 bit differences in the ciphertext) after only six rounds. Performance on a modern desktop computer or workstation is very impressive.

You can obtain a copy of Roger Needham and David Wheeler's original paper describing TEA, from the Security Group ftp site at the world-famous Cambridge Computer Laboratory at Cambridge University. There is also a paper on extended variants of TEA which addresses a couple of minor weaknesses (irrelevant in almost all real-world applications), and introduces a block variant of the algorithm which can be even faster in some circumstances.

TEA is very secure. There have been no known successful cryptanalyses of TEA. It is believed (by James Massey) to be as secure as the IDEA algorithm, designed by Massey and Xuejia Lai. It uses the same mixed algebraic groups technique as IDEA, but it is much simpler, hence

faster. Also, it is public domain, whereas IDEA is patented by Ascom-Tech AG in Switzerland. IBM's Don Coppersmith and Massey independently showed that mixing operations from orthogonal algebraic groups performs the diffusion and confusion functions that a traditional block cipher would implement with P- and S-boxes. As a simple drop-in encryption routine, it is great. The code is lightweight and portable enough to be used just about anywhere. It even makes a great random number generator for Monte Carlo simulations and the like. The minor weaknesses identified by David Wagner at Berkeley are unlikely to have any impact in the real world, and you can always implement the new variant TEA which addresses them. If you want a low-overhead end-to-end cipher (for real-time data, for example), then TEA fits the bill.

The 128 bit key used in the TEA is handled in 4th Dimension through four (4) longint values. The spread use of the four longint values provides a full 128 bit key that maintains all of the advantages afforded by use of the TEA. A single routine for generating a full 128 bit key from a block of source text is provided merely for the convenience of the developer.

**Note:** the CRYPT module was added in BASH v1.5.5.



## **CRYPT\_Decrypt\_TEA\_x**

**CRYPT\_Decrypt\_TEA\_x** ( *Encrypted Text ; First TEA Key ; Second TEA Key ; Third TEA Key ; Fourth TEA Key* ) => *Decrypted Text*

**CRYPT\_Decrypt\_TEA\_x**

```
(
    -> Encrypted Text : Text
    -> First TEA Key : Longint
    -> Second TEA Key : Longint
    -> Third TEA Key : Longint
    -> Fourth TEA Key : Longint
)
=> Decrypted Text: Text
```

| <b>Parameter</b>      | <b>Type</b> | <b>Description</b>   |
|-----------------------|-------------|--|
| <i>Encrypted Text</i> | Text        | Encrypted text which is to be decrypted                                  |
| <i>First TEA Key</i>  | Longint     | First TEA key which was used to encrypt text                             |
| <i>Second TEA Key</i> | Longint     | Second TEA key which was used to encrypt text                            |
| <i>Third TEA Key</i>  | Longint     | Third TEA key which was used to encrypt text                             |
| <i>Fourth TEA Key</i> | Longint     | Fourth TEA key which was used to encrypt text                            |
| <i>Decrypted Text</i> | Text        | Supplied source text decrypted using TEA algorithm and supplied TEA keys |

The method *CRYPT\_Decrypt\_TEA\_x* will decrypt a supplied text value using the supplied keys for the decryption. The decryption is done using the tiny encryption algorithm, documented above.

*Encrypted Text* is the text value which is to be decrypted using the tiny encryption algorithm.

*First TEA Key* is the first block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Second TEA Key* is the second block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Third TEA Key* is the third block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Fourth TEA Key* is the fourth and final block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Decrypted Text* is the decrypted text of *Encrypted Text* using the supplied keys for the tiny encryption algorithm. No checks are done for whether the supplied keys were actually used originally for the encryption; rather, the

decryption processing is run blind using the supplied keys and the result is then made available.

**Note:** the method *CRYPT\_Decrypt\_TEA\_x* was added in BASH v1.5.5.



## **CRYPT\_Decrypt\_TEA\_z**

**CRYPT\_Decrypt\_TEA\_z** ( *Referenced Encrypted BLOB ; Referenced Decrypted BLOB ; First TEA Key ; Second TEA Key ; Third TEA Key ; Fourth TEA Key* )

### **CRYPT\_Decrypt\_TEA\_z**

(  
    -> *Referenced Encrypted BLOB* : **Pointer**  
    -> *Referenced Decrypted BLOB* : **Pointer**  
    -> *First TEA Key* : **Longint**  
    -> *Second TEA Key* : **Longint**  
    -> *Third TEA Key* : **Longint**  
    -> *Fourth TEA Key* : **Longint**  
)

| <b>Parameter</b>                 | <b>Type</b>    | <b>Description</b>  |
|----------------------------------|----------------|---|
| <i>Referenced Encrypted BLOB</i> | <b>Pointer</b> | Referenced source BLOB which is to be decrypted   |
| <i>Referenced Decrypted BLOB</i> | <b>Pointer</b> | Referenced BLOB to hold source BLOB decrypted using TEA algorithm and supplied TEA keys |
| <i>First TEA Key</i>             | <b>Longint</b> | First TEA key which was used to encrypt BLOB  |
| <i>Second TEA Key</i>            | <b>Longint</b> | Second TEA key which was used to encrypt BLOB   |
| <i>Third TEA Key</i>             | <b>Longint</b> | Third TEA key which was used to encrypt BLOB  |
| <i>Fourth TEA Key</i>            | <b>Longint</b> | Fourth TEA key which was used to encrypt BLOB   |

The method *CRYPT\_Decrypt\_TEA\_z* will decrypt a referenced binary value using the supplied keys for the decryption. The decryption is done using the tiny encryption algorithm, documented above.

*Referenced Encrypted BLOB* is a pointer to the binary value which is to be decrypted using the tiny encryption algorithm.

*Referenced Decrypted BLOB* is pointer to the BLOB to contain the decrypted *Referenced Encrypted BLOB* using the supplied keys for the tiny encryption algorithm. No checks are done for whether the supplied keys were actually used originally for the encryption; rather, the decryption processing is run blind using the supplied keys and the result is then made available.

*First TEA Key* is the first block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Second TEA Key* is the second block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Third TEA Key* is the third block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

*Fourth TEA Key* is the fourth and final block of 32 bits (MSB to LSB) of the TEA key used to encrypt the data using the tiny encryption algorithm.

**Note:** the method *CRYPT\_Decrypt\_TEA\_z* was added in BASH v1.5.5.



## **CRYPT\_Encrypt\_TEA\_x**

**CRYPT\_Encrypt\_TEA\_x** ( *Source Text* ; *First TEA Key* ; *Second TEA Key* ;  
*Third TEA Key* ; *Fourth TEA Key* ) => *Encrypted Source Text*

**CRYPT\_Encrypt\_TEA\_x**

(

- > *Source Text* : **Text**
- > *First TEA Key* : **Longint**
- > *Second TEA Key* : **Longint**
- > *Third TEA Key* : **Longint**



-> *Fourth TEA Key* : Longint  
 )  
 => *Encrypted Source Text*: Text

| Parameter                    | Type    | Description  |
|------------------------------|---------|--|
| <i>Source Text</i>           | Text    | Source text which is to be encrypted                                     |
| <i>First TEA Key</i>         | Longint | First TEA key which was used to encrypt text                             |
| <i>Second TEA Key</i>        | Longint | Second TEA key which was used to encrypt text                            |
| <i>Third TEA Key</i>         | Longint | Third TEA key which was used to encrypt text                             |
| <i>Fourth TEA Key</i>        | Longint | Fourth TEA key which was used to encrypt text                            |
| <i>Encrypted Source Text</i> | Text    | Supplied source text encrypted using TEA algorithm and supplied TEA keys |

The method *CRYPT\_Encrypt\_TEA\_x* will encrypt a supplied text value using the supplied keys for the encryption. The encryption is done using the tiny encryption algorithm, documented above.

*Source Text* is the text value which is to be encrypted using the tiny encryption algorithm.

*First TEA Key* is the first block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Second TEA Key* is the second block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Third TEA Key* is the third block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Fourth TEA Key* is the fourth and final block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Encrypted Source Text* is the encrypted text of *Source Text* using the supplied keys for the tiny encryption algorithm.

**Note:** the method *CRYPT\_Encrypt\_TEA\_x* was added in BASH v1.5.5.



## **CRYPT\_Encrypt\_TEA\_z**

**CRYPT\_Encrypt\_TEA\_z** ( *Referenced Source BLOB ; Referenced Encrypted BLOB ; First TEA Key ; Second TEA Key ; Third TEA Key ; Fourth TEA Key* )

**CRYPT\_Encrypt\_TEA\_z**

(  
    -> *Referenced Source BLOB* : **Pointer**  
    -> *Referenced Encrypted BLOB* : **Pointer**  
    -> *First TEA Key* : **Longint**  
    -> *Second TEA Key* : **Longint**  
    -> *Third TEA Key* : **Longint**  
    -> *Fourth TEA Key* : **Longint**  
)

| <b>Parameter</b>                 | <b>Type</b>    | <b>Description</b>  |
|----------------------------------|----------------|---|
| <i>Referenced Source BLOB</i>    | <b>Pointer</b> | Referenced source BLOB which is to be encrypted   |
| <i>Referenced Encrypted BLOB</i> | <b>Pointer</b> | Referenced BLOB to hold source BLOB encrypted using TEA algorithm and supplied TEA keys |
| <i>First TEA Key</i>             | <b>Longint</b> | First TEA key which was used to encrypt BLOB  |
| <i>Second TEA Key</i>            | <b>Longint</b> | Second TEA key which was used to encrypt BLOB   |
| <i>Third TEA Key</i>             | <b>Longint</b> | Third TEA key which was used to encrypt BLOB  |
| <i>Fourth TEA Key</i>            | <b>Longint</b> | Fourth TEA key which was used to encrypt BLOB   |

The method *CRYPT\_Encrypt\_TEA\_z* will encrypt a referenced binary value using the supplied keys for the encryption. The encryption is done using the tiny encryption algorithm, documented above.

*Referenced Source BLOB* is a pointer to the binary value which is to be encrypted using the tiny encryption algorithm.

*Referenced Encrypted BLOB* is pointer to the BLOB to contain the encrypted *Referenced Source BLOB* using the supplied keys for the tiny encryption algorithm.

*First TEA Key* is the first block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Second TEA Key* is the second block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Third TEA Key* is the third block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

*Fourth TEA Key* is the fourth and final block of 32 bits (MSB to LSB) of the TEA key to be used to encrypt the data using the tiny encryption algorithm.

**Note:** the method *CRYPT\_Encrypt\_TEA\_z* was added in BASH v1.5.5.



## **CRYPT\_Get\_TEA\_Keys\_f\_Text**

**CRYPT\_Get\_TEA\_Keys\_f\_Text** ( *Source Text Key* ; *Referenced First TEA Key* ; *Referenced Second TEA Key* ; *Referenced Third TEA Key* ; *Referenced Fourth TEA Key* )

**CRYPT\_Get\_TEA\_Keys\_f\_Text**

```
(  
    -> Source Text Key : Text  
    -> Referenced First TEA Key : Pointer  
    -> Referenced Second TEA Key : Pointer  
    -> Referenced Third TEA Key : Pointer  
    -> Referenced Fourth TEA Key : Pointer  
)
```

| <b>Parameter</b>                 | <b>Type</b> | <b>Description</b>   |
|----------------------------------|-------------|--|
| <i>Source Text Key</i>           | Text        | Source key text to be used to generated TEA encryption keys    |
| <i>Referenced First TEA Key</i>  | Pointer     | Referenced first TEA key calculated from supplied source text  |
| <i>Referenced Second TEA Key</i> | Pointer     | Referenced second TEA key calculated from supplied source text |
| <i>Referenced Third TEA Key</i>  | Pointer     | Referenced thid TEA key calculated from supplied source text   |
| <i>Referenced Fourth TEA Key</i> | Pointer     | Referenced fourth TEA key calculated from supplied source text |

The method *CRYPT\_Get\_TEA\_Keys\_f\_Text* will generate a set of valid tiny encryption algorithm 32 bit blocks (longints) from a block of supplied text for use as keys into the tiny encryption algorithm.

The keys generated are unique to the supplied source text and are fully regenerative. The keys are generated using a modified version of the MD5 hash algorithm. the generated keys are reasonably random to provide affordable security using the tiny encryption alogorithm without compromising randomness.

*Source Key Text* is the text value to use to generate the TEA keys. Repeated use of the exact same text value will produce the same TEA keys. *Source Key Text* must be at least 22 bytes long and can consist only of uppercase letters, lowercase letters, numerals, space, and hyphens. All other byte values are invalid.

*Referenced First TEA Key* is a pointer to a longint to hold the first 32 bit block (MSB to LSB) of the 128 bit TEA key generated in this method.

*Referenced Second TEA Key* is a pointer to a longint to hold the second 32 bit block (MSB to LSB) of the 128 bit TEA key generated in this method.

*Referenced Third TEA Key* is a pointer to a longint to hold the third 32 bit block (MSB to LSB) of the 128 bit TEA key generated in this method.

*Referenced Fourth TEA Key* is a pointer to a longint to hold the fourth and final 32 bit block (MSB to LSB) of the 128 bit TEA key generated in this method.

**Note:** the method *CRYPT\_Get\_TEA\_Keys\_f\_Text* was added in BASH v1.5.5.

# DATE Module

The DATE module provides very basic date operations which are currently needed in 4th Dimension. To a large extent, the DATE module acts as a bridge to other modules and functionality commonly used. Though it is the preference of the authors to utilize the DTS system exclusively for handling date and time values in 4D, the methods provided in the DATE module make this task much easier.

**Note:** the DATE module was added in BASH v1.5.4.



## **DATE\_Get\_ISO8601\_GMT**

**DATE\_Get\_ISO8601\_GMT** (*DTS Value* ) => *ISO 8601 DateTime Value*

**DATE\_Get\_ISO8601\_GMT**

(  
    -> *DTS Value* : **String [14]**  
)  
    => *ISO 8601 DateTime Value* : **Text**

| <b>Parameter</b>               | <b>Type</b>        | <b>Description</b>  |
|--------------------------------|--------------------|---|
| <i>DTS Value</i>               | <b>String [14]</b> | DTS value to convert to ISO 8601 formatted datetime value |
| <i>ISO 8601 DateTime Value</i> | <b>Text</b>        | ISO 8601 formatted datetime value                         |

The method **DATE\_Get\_ISO8601\_GMT** return a properly formatted ISO 8601 datetime stamp corresponding to a specified DTS value.

*DTS Value* is a valid DTS value which will be used to generate a properly formatted ISO 8601 datetime stamp.

*ISO 8601 DateTime Value* is a properly formatted ISO 8601 datetime stamp for the value *DTS Value* , assumed to be a GMT specified DTS value. ISO 8601 formatted values have the following format:

yyyy-mm-ddThh:mm:ssZ

**Note:** the method *DATE\_Get\_ISO8601\_GMT* was added in BASH v1.5.8.



## **DATE\_Get\_Month\_f\_ShortName**

*DATE\_Get\_Month\_f\_ShortName* ( *Month Short Name* ) => *Month Number*

*DATE\_Get\_Month\_f\_ShortName*  
(  
    -> *Month Short Name* : **Text**  
)  
    => *Month Number* : **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>                                    |
|-------------------------|----------------|---|
| <i>Month Short Name</i> | <b>Text</b>    | Short textual name of month (see RFC 822)             |
| <i>Month Number</i>     | <b>Longint</b> | Month number corresponding to <i>Month Short Name</i> |

The method *DATE\_Get\_Month\_f\_ShortName* will return the month number for a specified textual month short name.

*Month Short Name* is the textual short month name to get the month number for. See RFC 822 for details on short month names, available from:

[http://www.deepskytech.com/rfcs/rfc\\_0822.txt](http://www.deepskytech.com/rfcs/rfc_0822.txt)

*Month Number* is the month number corresponding to *Month Short Name* . If *Month Short Name* is not a valid short month name then *Month Number* will be set to negative one (-1).

**Note:** the method *DATE\_Get\_Month\_f\_ShortName* was added in BASH v1.5.8.



## **DATE\_Get\_RFC\_GMT**

**DATE\_Get\_RFC\_GMT** ( *Local Date* ; *Local Time* ; *Referenced GMT Date* ;  
*Referenced GMT Time* ) => RFC Formatted GMT Date Time Stamp

**DATE\_Get\_RFC\_GMT**

(  
    -> *Local Date* : **Date**  
    -> *Local Time* : **Time**  
    -> *Referenced GMT Date* : **Pointer**  
    -> *Referenced GMT Time* : **Pointer**  
)  
=> RFC Formatted GMT Date Time Stamp : **Text**

| <b>Parameter</b>                         | <b>Type</b>    | <b>Description</b>  |
|--|----------------|---|
| <i>Local Date</i>                        | <b>Date</b>    | Date value to use for calculations  |
| <i>Local Time</i>                        | <b>Time</b>    | Time value to use for calculations  |
| <i>Referenced GMT Date</i>               | <b>Pointer</b> | Reference to date variable to hold <i>Local Date</i> in GMT               |
| <i>Referenced GMT Time</i>               | <b>Pointer</b> | Reference to time variable to hold <i>Local Time</i> in GMT               |
| <i>RFC Formatted GMT Date Time Stamp</i> | <b>Text</b>    | RFC formatted date time stamp for <i>Local Date</i> and <i>Local Time</i> |

The method **DATE\_Get\_RFC\_GMT** will format specified date and time values as a standard RFC formatted date time stamp. The time zone on the local machine will be used to convert the date and time values to GMT. The GMT converted date and time values can also be returned in separated referenced variables. Specifications for the RFC formatted date time stamps are available in RFC 822, available at:

[http://www.deepskytech.com/rfcs/rfc\\_0822.txt](http://www.deepskytech.com/rfcs/rfc_0822.txt)

*Local Date* is the local date value to use for the conversions.

*Local Time* is the local time value to use for the conversions.

*Referenced GMT Date* is a reference to a date variable to contain the the GMT equivalent of *Local Date* and *Local Time* . The time zone of the local machine will be used



to make the conversion. If *Referenced GMT Date* is NULL, then no converted date value will be returned.

*Referenced GMT Time* is a reference to a time variable to contain the the GMT equivalent of *Local Date* and *Local Time* . The time zone of the local machine will be used to make the conversion. If *Referenced GMT Time* is NULL, then no converted time value will be returned.

*RFC Formatted GMT Date Time Stamp* is the string of a properly formatted date time stamp (as specified by RFC 822). *Local Date* and *Local Time* will be converted to GMT according to the time zone settings of the local machine, and then these values will be used to construct the properly formatted string.

**Note:** the method *DATE\_Get\_RFC\_GMT* was added in BASH v1.5.4.



## **DATE\_Make\_from\_Values**

**DATE\_Make\_from\_Values** ( *Year Value* ; *Month Value* ; *Day Value* ) =>  
*Date Value*

**DATE\_Make\_from\_Values**  
(  
    -> *Year Value* : Longint  
    -> *Month Value* : Longint  
    -> *Day Value* : Longint  
)  
=> *Date Value* : Date

| Parameter          | Type    | Description  |
|--------------------|---------|--|
| <i>Year Value</i>  | Longint | Full numeric year value  |
| <i>Month Value</i> | Longint | Full numeric month value (between one and twelve, in most cases) |
| <i>Day Value</i>   | Longint | Full numeric day value   |
| <i>Date Value</i>  | Date    | Properly formatted 4D date value for values specified            |

The method *DATE\_Make\_from\_Values* will create a properly formatted 4D date variable with the values specified. The actual date format settings for the local

machine will be bypassed, allowing for the creation of a properly formatted 4D date value regardless of platform, machine, and/or local user settings. The resulting date value created will not be normalized.

*Year Value* is the full numeric year value to be used to create the 4D date value. No abbreviations are allowed in this value, as the date variable is constructed directly from this value (e.g. 99 is interpreted as the year 99, not the year 1999).

*Month Value* is the full numeric month value to be used to create the 4D date value. The native 4D constants, **Days** and **Months** can be used for values, though there is no restriction that this value be between one (1) and twelve (12).

*Day Value* is the full numeric day value to be used to create the 4D date value. *Day Value* is consider to be the day of the month. Often, this value will inclusively be between one (1) and the number of days in the specified month. Though, there are no restrictions placed on the value of *Day Value*.

*Date Value* is the properly constructed 4D date value for the values specified in *Year Value*, *Month Value*, and *Day Value*. *Date Value* is not normalized; rather, the specified values are used to directly construct the 4D date value. Machine, OS, and local user settings are bypassed, allowing for the creation of a proper 4D date value regardless of the date format settings on the local machine.

#### Example:

The following table shows different values passed to the method *DATE\_Make\_from\_Values* and the results which are returned. The results are displayed using the format "yyyy/mm/dd" in the table. The far right column in the table contains the normalized results (see the note, below, about nromalizing 4D date values).

| Y | M | D | Result | Result (Norm.) |
|---|---|---|--------|----------------|
|---|---|---|--------|----------------|

|      |    |    |            |            |
|------|----|----|------------|------------|
| 1999 | 4  | 15 | 1999/04/15 | 1999/04/15 |
| 2000 | 2  | 29 | 2000/02/29 | 2000/02/29 |
| 2000 | 2  | 30 | 2000/02/30 | 2000/03/01 |
| 2001 | 12 | 31 | 2001/12/31 | 2001/12/31 |
| 2001 | 12 | 35 | 2001/12/35 | 2002/01/04 |

**Note:** to normalize a 4th Dimension date value, merely add zero (0) to it.

**Note:** the method *DATE\_Make\_from\_Values* was added in BASH v1.5.4.

## DSS Module

The DSS module is probably the single most used module of code which we have ever developed in 4th Dimension. It provides functionality which is exceedingly useful for any 4D programmer, regardless of the particular coding style and conventions used.

The simplicity of the DSS module is what helps make it so universally applicable. There are really only two methods to be called in the DSS module. And, the functionality within these two methods is very compact. But, the practical functionality gained is immeasurable.

Basically, the DSS module provides a means for a central pool of variables of every type to be shared across your 4th Dimension application. Whenever a variable of a particular type is needed, it can be retrieved from the DSS module for use. Once the variable is done being used, it can be returned to the DSS module for future use by other areas of your code. The variable management system within the DSS module provides a locking mechanism for each variable which is currently in use; the DSS module will not return to be used a variable which is still being used within another area of your code.

Consistent use of the DSS module can easily lead you to no longer require as many process and interprocess variables within your 4D based applications. And, it can even alleviate the commonly held shortcoming of 4D's lack of references to local variables.

**Note:** as of version 1.4.6 of BASH, one hundred (100) variables of each type can be used concurrently.

**Note:** as of version 1.5.5 of BASH, two hundred (200) variables of each of the following types can be used concurrently: text, longint, BLOB, text array, and longint array.

## Variable Classifications

It is worth knowing, also, that variable types in 4th Dimension have two different classifications: unary and array. Unary variables are capable of storing a single data value. Array variables are capable of storing zero, one, or more data values.

A complete listing of the unary variable types and their equivalent array data types follows, including the actual DSS variable types which used (separate unary or array data types are used within DSS):

| <u>Unary</u> | <u>Array</u> | <u>DSS</u>  |
|--------------|--------------|---|
| BLOB         | n/a          | <i>BLOB (unary only)</i>                                |
| Boolean      | Boolean      | Boolean   |
| Date         | Date         | Date  |
| Graph        | n/a          | <i>Graph (unary only)</i>                               |
| Integer      | Integer      | Integer   |
| Longint      | Longint      | Longint   |
| Picture      | Picture      | Picture   |
| Pointer      | Pointer      | Pointer   |
| Real         | Real         | Real  |
| String       | String       | <i>Text</i>   |
| Text         | Text         | Text  |
| Time         | Longint      | <i>Time (unary only)</i><br><i>Longint (array only)</i> |



### **DSS\_ERROR**

**DSS\_ERROR** ( *BASh* Error Number; *Special Error Text*; *Calling Method Name* )

#### **DSS\_ERROR**

(  
-> *BASh* Error Number: **Longint**  
-> *Special Error Text*: **Text**  
-> *Calling Method Name*: **Text**  
)

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>                                |
|---------------------------|----------------|---|
| <i>BASh</i> Error Number  | <b>Longint</b> | Internal <i>BASh</i> error number                 |
| <i>Special Error Text</i> | <b>Text</b>    | Special text to describe the exact error instance |

| Calling Method Name | Text | Name of the method that the error condition occurred in |
|---------------------|------|---|
|---------------------|------|---|

The method ***DSS\_ERROR*** acts as a callback method from within the DSS module for errors that may occur. Any time an error condition is detected within the DSS module, a call to the method ***DSS\_ERROR*** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the DSS method which call the ***DSS\_ERROR*** method.

The ***DSS\_ERROR*** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.



## **DSS\_Get\_Array\_by\_Unary\_Type**

***DSS\_Get\_Array\_by\_Unary\_Type*** ( *Unary Type*;) => *Referenced DSS Array Variable*

***DSS\_Get\_Array\_by\_Unary\_Type***  
 (  
     -> *Unary Type*: Longint  
 )  
     => *Referenced DSS Array Variable*: Pointer

| Parameter                            | Type    | Description   |
|--------------------------------------|---------|---|
| <i>Unary Type</i>                    | Longint | Type of array variable wanted (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |
| <i>Referenced DSS Array Variable</i> | Pointer | Reference to DSS array variable to be used matching type of <i>Unary Type</i>   |

The method *DSS\_Get\_Array\_by\_Unary\_Type* will return a reference to an available DSS array variable matching the type supplied. Unary variable types will have the array equivalent DSS variable type returned for use. This variable is locked within the DSS module from being returned as a variable which can be used by subsequent calls to any of the *DSS\_Get\_* methods.

*Unary Type* is the unary data type desired. Array variable types can also be passed to this routine, for convenience.

*Referenced DSS Array Variable* is a pointer to a DSS array variable matching the type requested. If all DSS variables of a given type are locked and a subsequent call to any of the *DSS\_Get\_* methods is made, a NULL pointer is returned.

It is a mandatory that once a DSS variable is done being utilized that it be returned to the pool of available variables by calling *DSS\_Return\_Variable*. Failure to do so may result in an error condition.

See the method *DSS\_Get\_Variable\_by\_Type* for a more detailed explanation of the variable usage within the DSS module.

**Note:** the method *DSS\_Get\_Array\_by\_Unary\_Type* was added in BASH v1.5.1.



## **DSS\_Get\_Unary\_by\_Array\_Type**

***DSS\_Get\_Unary\_by\_Array\_Type*** ( Array Type;) => *Referenced DSS Unary Variable*

***DSS\_Get\_Unary\_by\_Array\_Type***

(

-> Array Type: Longint

)

=> *Referenced DSS Unary Variable: Pointer*

| Parameter | Type | Description |
|-----------|------|-------------|
|-----------|------|-------------|

|                                      |                |   |
|--------------------------------------|----------------|---|
| <i>Array Type</i>                    | <i>Longint</i> | Type of unary variable wanted (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |
| <i>Referenced DSS Unary Variable</i> | <i>Pointer</i> | Reference to DSS unary variable to be used matching type of <i>Array Type</i>   |

The method ***DSS\_Get\_Unary\_by\_Array\_Type*** will return a reference to an available DSS unary variable matching the type supplied. Array variable types will have the unary equivalent DSS variable type returned for use. This variable is locked within the DSS module from being returned as a variable which can be used by subsequent calls to any of the *DSS\_Get\_* methods.

*Array Type* is the array data type desired. Unary variable types can also be passed to this routine, for convenience.

*Referenced DSS Unary Variable* is a pointer to a DSS unary variable matching the type requested. If all DSS variables of a given type are locked and a subsequent call to any of the *DSS\_Get\_* methods is made, a NULL pointer is returned.

It is a mandatory that once a DSS variable is done being utilized that it be returned to the pool of available variables by calling ***DSS\_Return\_Variable***. Failure to do so may result in an error condition.

See the method ***DSS\_Get\_Variable\_by\_Type*** for a more detailed explanation of the variable usage within the DSS module.

**Note:** the method ***DSS\_Get\_Unary\_by\_Array\_Type*** was added in BASH v1.5.1.



## **DSS\_Get\_Variable\_by\_Type**

***DSS\_Get\_Variable\_by\_Type*** ( *Variable Type* ) => *Referenced DSS Variable*

***DSS\_Get\_Variable\_by\_Type***



```
(
    -> Variable Type: Longint
)
=> Referenced DSS Variable: Pointer
```

| Parameter               | Type    | Description   |
|-------------------------|---------|---|
| Variable Type           | Longint | Type of variable wanted (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |
| Referenced DSS Variable | Pointer | Reference to DSS variable to be used matching type of <i>Variable Type</i>  |

The method ***DSS\_Get\_Variable\_by\_Type*** returns a reference to a variable matching the type of *Variable Type*. This variable is locked within the DSS module from being returned as a variable which can be used by subsequent calls to ***DSS\_Get\_Variable\_by\_Type***.

The DSS module supports every variable type which is supported by 4th Dimension, with the sole exception of 2D arrays.

For each variable type which can be requested, the DSS module has a pool of one hundred (100) variables to select from. If all DSS variables of a given type are locked and a subsequent call to ***DSS\_Get\_Variable\_by\_Type*** is made, a NULL pointer is returned.

**Note:** as of version 1.5.5 of BASH, two hundred (200) variables of each of the following types can be used concurrently: text, longint, BLOB, text array, and longint array.

DSS variables which are put into use within code will be locked from being returned as available variables. Calling the DSS method ***DSS\_Return\_Variable*** will return a DSS variable to the pool of available variables, effectively unlocking it for subsequent use.

It is a mandatory that once a DSS variable is done being utilized that it be returned to the pool of available

variables by calling *DSS\_Return\_Variable*. Failure to do so may result in an error condition.

### Example:

The following snippet of code shows a short example of properly using the *DSS\_Get\_Variable\_by\_Type* method in place of references to local variables:

```
`FUNCTION: FILE_qi_Volume_Exists
`
`This will make sure that a volume exists
`
`$0 is qi for volume
`  = 0 volume does not exist
`  = 1 volume does exist
`$1 is the volume name to check
`

C_LONGINT ($0)
$0:=0 `default to doesn't exist
C_TEXT($1;$xVolumeName)
$xVolumeName:=$1
`

C_POINTER ($pVolumes)
C_LONGINT ($iIndex)
`

`get a temp var from the dss
$pVolumes:=DSS_Get_Variable_by_Type (Text array )
`get all of the current volumes
FILE_Get_All_VolumeNames ($pVolumes)
`check to see if the volume exists
$iIndex:=Find in array ($pVolumes->$xVolumeName;1)
If ($iIndex#-1)
  $0:=1
End if
`clean up
DSS_Return_Variable ($pVolumes)
`eof
```

The method *FILE\_Get\_All\_VolumeNames* requires a reference to a text array to get the list of all volumes. Instead of wasting a process or interprocess variable specifically for this method call, the DSS module provides a temporary text array as referenced by the variable \$pVolumes. This text array is used to get the list of volume names, then searched on to find a specific volume name. Once done, the text array is returned to the pool of available DSS variables for use elsewhere.



## DSS\_Return\_Variable

**DSS\_Return\_Variable** ( *Referenced DSS Variable* )

**DSS\_Return\_Variable**

(  
    -> *Referenced DSS Variable: Pointer*  
)

| Parameter                      | Type    | Description   |
|--------------------------------|---------|---|
| <i>Referenced DSS Variable</i> | Pointer | Reference to DSS variable to be returned to pool of available DSS variables |

The method **DSS\_Return\_Variable** will return a variable to the pool of available variables within the DSS module. It should be called after using a DSS variable which was acquired from the method **DSS\_Get\_Variable\_by\_Type**.

## DTS Module

The DTS (Date-Time Stamps) module contains routines for creating, handling, and manipulating DTS values. The code within the DTS module is exceedingly simple to implement in 4th Dimension, providing basic DTS functionality needed in any system.

### DTS Values

A DTS value is merely a fourteen (14) byte string which contains a date and time value. The format for a DTS value is as follows:

YYYYMMDDhhmmss

where

*YYYY* is four (4) byte year value (e.g. "1970")

*MM* is two (2) byte month value (e.g. "04")

*DD* is two (2) byte day value (e.g. "15")

*hh* is two (2) byte hour value (e.g. "18")

*mm* is two (2) byte minute value (e.g. "39")

*ss* is two (2) byte second value (e.g. "13")

So, for example, a DTS value of "19700415183913" would translate to April 15th, 1970, at 6:39:13 in the afternoon.

DTS value have a significant advantage over native date and time values in 4th Dimension. The advantages include:

- i) Sortability on a single, indexed field value for true chronological ordering;
- ii) Consistent storage format for date and time values, regardless of localization or machine settings;
- iii) Encoding format for DTS values is easily human readable;

- iv) Interfaces can continue to use standard date and time values, merely encoding into a DTS value for storage and usage internally within the database and code;
- v) Date and time math can now be accomplished much more easily and consistently;
- vi) The DTS system is often considered easier to understand and handle, especially when considering the large number of "gotchas" when dealing with native date and time values in 4th Dimension.

With repeated, consistent use of DTS values and the DTS module, every 4D programmer can realise significant gains in legibility and functionality when dealing with date and time values. As well, maintenance is significantly reduced as DTS values are easier to understand and deal with, thereby making it much simpler to produce error free code for handling date and time values. As well, since the DTS value type is completely contrived, there are no restrictions on how it can be utilized and implemented in 4th Dimension; you are free to utilize the concepts and routines within the DTS module to maximize the potential of each system placed into production.

**Note:** the DTS module was initially added in BASH v1.4.7.



## **DTS\_Add**

*DTS\_Add( Primary DTS Value; Secondary DTS Value) => Summed DTS Value*

```
DTS_Add
(
    -> Primary DTS Value: String[14]
-> Secondary DTS Value: String[14]
)
    => Summed DTS Value: String[14]
```

| <b>Parameter</b> | <b>Type</b> | <b>Description</b> |
|------------------|-------------|--------------------|
|------------------|-------------|--------------------|

|                            |            |                    |
|----------------------------|------------|--------------------|
| <i>Primary DTS Value</i>   | String[14] | First DTS addend   |
| <i>Secondary DTS Value</i> | String[14] | Second DTS addend  |
| <i>Summed DTS Value</i>    | String[14] | Sum of DTS addends |

The method ***DTS\_Add*** will add together two DTS values and return a DTS value wherein only the time values are normalized.

*Primary DTS Value* and *Secondary DTS Value* are both valid DTS values which are to be added.

*Summed DTS Value* is a well formed addition of *Primary DTS Value* and *Secondary DTS Value*. Only the time portion of *Summed DTS Value* is normalized.

#### Example:

The following table shows the values of two addends and the results which will be returned from the method ***DTS\_Add***:

| <u>1st Addend</u> | <u>2nd Addend</u> | <u>Sum</u>     |
|-------------------|-------------------|----------------|
| 20001122040506    | 00000000010101    | 20001122050607 |
| 20001122040506    | 00000014000000    | 20001136040506 |
| 20001031040506    | 00000100000000    | 20001131040506 |
| 20000229040506    | 00010000000000    | 20010229040506 |
| 20001122040506    | 00000000200000    | 20001123000506 |

As can be seen by the above table, DTS values need not respect the rules of being well formed as date and time values often must in 4th Dimension. If a DTS value must be incremented by a certain amount, for instance by fourteen (14) days (i.e. two weeks), a single month, or merely twenty (20) hours, just it is as simple as creating a DTS value with only the amount to be incremented (use the method ***DTS\_Make\_from\_Values***, detailed below) and adding it to the original DTS value by using the ***DTS\_Add*** method.

**Note:** the method ***DTS\_Add*** was added in BASH v1.4.7.



## DTS\_Add\_Normalize

*DTS\_Add\_Normalize* ( *Primary DTS Value* ; *Secondary DTS Value* ) =>  
*Summed DTS Value*

*DTS\_Add\_Normalize*

(  
-> *Primary DTS Value*: String[14]  
-> *Secondary DTS Value*: String[14]  
)  
=> *Summed DTS Value*: String[14]

| Parameter                  | Type       | Description        |
|----------------------------|------------|--------------------|
| <i>Primary DTS Value</i>   | String[14] | First DTS addend   |
| <i>Secondary DTS Value</i> | String[14] | Second DTS addend  |
| <i>Summed DTS Value</i>    | String[14] | Sum of DTS addends |

The method *DTS\_Add\_Normalize* will add together two DTS values and return a DTS value wherein both the date and time values are normalized.

*Primary DTS Value* and *Secondary DTS Value* are both valid DTS values which are to be added.

*Summed DTS Value* is a well formed addition of *Primary DTS Value* and *Secondary DTS Value*. Both the date and time portions of *Summed DTS Value* are normalized.

### Example:

The following table shows the values of two addends and the results which will be returned from the method *DTS\_Add\_Normalize* :

| <u>1st Addend</u> | <u>2nd Addend</u> | <u>Sum</u>     |
|-------------------|-------------------|----------------|
| 20001122040506    | 00000000010101    | 20001122050607 |
| 20001122040506    | 00000014000000    | 20001206040506 |
| 20001031040506    | 00000100000000    | 20001201040506 |
| 20000229040506    | 00010000000000    | 20010301040506 |
| 20001122040506    | 00000000200000    | 20001123000506 |

As can be seen by the above table, DTS values need not respect the rules of being well formed as date and time values often must in 4th Dimension. If a DTS value must be incremented by a certain amount, for instance by fourteen (14) days (i.e. two weeks), a single month, or merely twenty (20) hours, just it is as simple as creating a DTS value with only the amount to be incremented (use the method *DTS\_Make\_from\_Values*, detailed below) and adding it to the original DTS value by using the *DTS\_Add\_Normalize* method.

**Note:** the method *DTS\_Add\_Normalize* was added in BASH v1.5.4.



## **DTS\_Convert\_f\_RFC**

***DTS\_Convert\_f\_RFC*** ( *RFC Formatted DateTime Stamp* ) => *DTS Value*

***DTS\_Convert\_f\_RFC***

```
(
    -> RFC Formatted DateTime Stamp :Text
)
=> DTS Value :String [14]
```

| <b>Parameter</b>                    | <b>Type</b> | <b>Description</b>   |
|-------------------------------------|-------------|--|
| <i>RFC Formatted DateTime Stamp</i> | Text        | RFC formatted value (see RFC 822)                              |
| <i>DTS Value</i>                    | String [14] | DTS value corresponding to <i>RFC Formatted DateTime Stamp</i> |

The method *DTS\_Convert\_f\_RFC* will convert a properly formatted RFC datetime stamp into a valid DTS value.

*RFC Formatted DateTime Stamp* is a properly formatted RFC datetime stamp which will be converted to a standard DTS value. See RFC 822 for details on properly formatted RFC datetime stamps, available from:

[http://www.deepskytech.com/rfcs/rfc\\_0822.txt](http://www.deepskytech.com/rfcs/rfc_0822.txt)



*DTS Value* is the DTS value corresponding to the value within *RFC Formatted DateTime Stamp* .

**Note:** the method *DTS\_Convert\_f\_RFC* was added in BASH v1.5.8.



## **DTS\_Get\_Current**

*DTS\_Get\_Current* => Current DTS Value

*DTS\_Get\_Current*  
=> Current DTS Value: String[14]

| Parameter         | Type       | Description   |
|-------------------|------------|---|
| Current DTS Value | String[14] | DTS value corresponding to the date and time on the current machine |

The method *DTS\_Get\_Current* returns a DTS value containing the currently set date and time as it exists on the current machine.

*Current DTS Value* will always be a well formed date.

Take care to note though that the date and time is retrieved from the current machine even when this method is called in a client/server environment; so, the client machine will never retrieve the date and time from the server when calling *DTS\_Get\_Current*.

If the current DTS value for the server is needed, use the method *DTS\_Make\_from\_DateTime* and native 4D commands to create the DTS value.

**Note:** the method *DTS\_Get\_Current* was added in BASH v1.4.7.



## **DTS\_Get\_Date**

*DTS\_Get\_Date*(DTS Value) => Date Value

## *DTS\_Get\_Date*

```
(  
    -> DTS Value: String[14]  
)  
=> Date Value: Date
```

| Parameter  | Type       | Description                                  |
|------------|------------|--|
| DTS Value  | String[14] | Valid DTS value                              |
| Date Value | Date       | Valid 4D date value extracted from DTS Value |

The method *DTS\_Get\_Date* will return a valid 4D date value in *Date Value* corresponding to the date stored in the supplied *DTS Value*.

*DTS Value* is any valid DTS value which the date is to be extracted from.

*Date Value* is a valid 4D date value. It is extracted from the date portion of *DTS Value* and returned as a result of *DTS\_Get\_Date*.

**Note:** the method *DTS\_Get\_Date* was added in BASH v1.4.7.



## **DTS\_Get\_Date\_Time**

*DTS\_Get\_Date\_Time*(DTS Value; Referenced Date Variable; Referenced Time Variable)

### *DTS\_Get\_Date\_Time*

```
(  
    -> DTS Value: String[14]  
    -> Referenced Date Variable: Pointer  
    -> Referenced Time Variable: Pointer  
)
```

| Parameter                | Type       | Description   |
|--------------------------|------------|---|
| DTS Value                | String[14] | Valid DTS value   |
| Referenced Date Variable | Pointer    | Reference to a 4D date variable to hold the date contained within DTS Value |

|                                 |                |  |
|---------------------------------|----------------|--|
| <i>Referenced Time Variable</i> | <b>Pointer</b> | <b>Reference to a 4D time variable to hold the time contained within DTS Value</b> |
|---------------------------------|----------------|--|

The method *DTS\_Get\_Date\_Time* will return in referenced date and time variables the date and time contained within a supplied DTS value.

*DTS Value* is any valid DTS value which the date and time is to be extracted from.

*Referenced Date Variable* and *Referenced Time Variable* are pointers to date and time variables, respectively. The date and time contained in *DTS Value* will be extracted and placed into *Referenced Date Variable* and *Referenced Time Variable*, respectively.

**Note:** the method *DTS\_Get\_Date\_Time* was added in BASH v1.4.7.



## DTS\_Get\_Day

*DTS\_Get\_Day*( *DTS Value*) => *Day Value*

```
DTS_Get_Day
(
    -> DTS Value: String[14]
)
=> Day Value: Longint
```

| <b>Parameter</b> | <b>Type</b> | <b>Description</b>                               |
|------------------|-------------|--|
| <i>DTS Value</i> | String[14]  | Valid DTS value                                  |
| <i>Day Value</i> | Longint     | Day value as stored in supplied <i>DTS Value</i> |

The method *DTS\_Get\_Day* returns the day value for a supplied DTS value.

*DTS Value* is any valid DTS value which the day value is to be extracted from.

*Day Value* is the day value that is stored in the supplied *DTS Value*.

**Note:** the method *DTS\_Get\_Day* was added in BASH v1.4.7.



## **DTS\_Get\_Maximum**

*DTS\_Get\_Maximum* => *Maximum DTS Value*

*DTS\_Get\_Maximum*  
=> *Maximum DTS Value: String[14]*

| Parameter                | Type       | Description                         |
|--------------------------|------------|-------------------------------------|
| <i>Maximum DTS Value</i> | String[14] | Maximum DTS value, "99991231235959" |

The method *DTS\_Get\_Maximum* returns the maximum valid DTS value which is allowed.

*Maximum DTS Value* is equivalent to "99991231235959".

**Note:** remember that it is perfectly acceptable to have DTS values in which individual elements exceed the maximum individual elements that exist in *Maximum DTS Value*. For instance, the DTS value "00002000000000" is completely acceptable and can be used to easily add twenty (20) months to any other DTS value using the method *DTS\_Add*.

**Note:** the method *DTS\_Get\_Maximum* was added in BASH v1.4.7.



## **DTS\_Get\_Month**

*DTS\_Get\_Month*( *DTS Value*) => *Month Value*

*DTS\_Get\_Month*  
(  
    -> *DTS Value: String[14]*  
)

=> *Month Value*: Longint

| Parameter          | Type       | Description  |
|--------------------|------------|--|
| <i>DTS Value</i>   | String[14] | Valid DTS value                                    |
| <i>Month Value</i> | Longint    | Month value as stored in supplied <i>DTS Value</i> |

The method *DTS\_Get\_Month* returns the month value for a supplied DTS value.

*DTS Value* is any valid DTS value which the month value is to be extracted from.

*Month Value* is the month value that is stored in the supplied *DTS Value*.

**Note:** the method *DTS\_Get\_Month* was added in BASH v1.4.7.



## **DTS\_Get\_Range**

*DTS\_Get\_Range*( *Reference DTS*; *Range Type*; *Referenced Beginning DTS*; *Referenced Ending DTS*)

*DTS\_Get\_Range*  
(  
-> *Reference DTS*: String[14]  
-> *Range Type*: Longint  
-> *Referenced Beginning DTS*: Pointer  
-> *Referenced Ending DTS*: Pointer  
)

| Parameter                       | Type       | Description  |
|---------------------------------|------------|--|
| <i>Reference DTS</i>            | String[14] | DTS value to reference from when calculating range         |
| <i>Range Type</i>               | Longint    | Type of range to calculate                                 |
| <i>Referenced Beginning DTS</i> | Pointer    | Pointer to DTS to place beginning of calculated range into |
| <i>Referenced Ending DTS</i>    | Pointer    | Pointer to DTS to place ending of calculated range into    |

The method *DTS\_Get\_Range* returns valid DTS values matching a specified range type in respect to a specified reference DTS value.

*Reference DTS* is a valid DTS value which will be used as the reference DTS to build *Referenced Beginning DTS* and *Referenced Ending DTS* values from.

*Range Type* is a selector value which will determine what range values will be returned in *Referenced Beginning DTS* and *Referenced Ending DTS*. Valid values for *Range Type* are:

| <i>Range Type</i> | Range returned |
|-------------------|----------------|
| 1                 | Last week      |
| 2                 | Last month     |
| 3                 | Last quarter   |

The following rule apply for range calculations:

- i) Weeks start on Sunday and end on Saturday;
- ii) Quarters work off of a standard calendar quarter;
- iii) Time values are always set to midnight for range types that involve values of a day or more.

More values for *Range Type* will be added in future versions of the BASH component.

**Note:** the method *DTS\_Get\_Range* was added in BASH v1.4.7.



## **DTS\_Get\_Time**

*DTS\_Get\_Time*(DTS Value) => Time Value

```
DTS_Get_Time
(
    -> DTS Value: String[14]
)
=> Time Value: Time
```

| Parameter         | Type       | Description   |
|-------------------|------------|---|
| <i>DTS Value</i>  | String[14] | Valid DTS value                                     |
| <i>Time Value</i> | Time       | Valid 4D time value extracted from <i>DTS Value</i> |

The method *DTS\_Get\_Time* will return a valid 4D time value in *Time Value* corresponding to the time stored in the supplied *DTS Value*.

*DTS Value* is any valid DTS value which the time is to be extracted from.

*Time Value* is a valid 4D time value. It is extracted from the time portion of *DTS Value* and returned as a result of *DTS\_Get\_Time* .

**Note:** the method *DTS\_Get\_Time* was added in BASH v1.4.7.



## **DTS\_Get\_Year**

*DTS\_Get\_Year*( *DTS Value*) => *Year Value*

```
DTS_Get_Year
(
    -> DTS Value: String[14]
)
=> Year Value: Longint
```

| Parameter         | Type       | Description                                       |
|-------------------|------------|---|
| <i>DTS Value</i>  | String[14] | Valid DTS value                                   |
| <i>Year Value</i> | Longint    | Year value as stored in supplied <i>DTS Value</i> |

The method *DTS\_Get\_Year* returns the year value for a supplied DTS value.

*DTS Value* is any valid DTS value which the year value is to be extracted from.

*Year Value* is the year value that is stored in the supplied *DTS Value*.

**Note:** the method *DTS\_Get\_Year* was added in BASH v1.4.7.

---

## **DTS\_Make\_from\_DateTime**

*DTS\_Make\_from\_DateTime*(*Date Value*; *Time Value*) => *DTS Value*

*DTS\_Make\_from\_DateTime*  
(  
    -> *Date Value*: **Date**  
    -> *Time Value*: **Time**  
)  
=> *DTS Value*: **String[14]**

| Parameter         | Type              | Description   |
|-------------------|-------------------|---|
| <i>Date Value</i> | <b>Date</b>       | Valid 4th Dimension date value                                      |
| <i>Time Value</i> | <b>Time</b>       | Valid 4th Dimension time value                                      |
| <i>DTS Value</i>  | <b>String[14]</b> | Valid DTS value formed from <i>Date Value</i> and <i>Time Value</i> |

The method *DTS\_Make\_from\_DateTime* will return a valid DTS value for supplied date and time values.

*Date Value* is a valid 4th Dimension date value.

*Time Value* is a valid 4th Dimension time value.

*DTS Value* is a valid DTS value formed from *Date Value* and *Time Value*.

**Note:** the method *DTS\_Make\_from\_DateTime* was added in BASH v1.4.7.

---

## **DTS\_Make\_from\_Values**

*DTS\_Make\_from\_Values*(*Years*; *Months*; *Days*; *Hours*; *Minutes*; *Seconds*) => *DTS Value*



## *DTS\_Make\_from\_Values*

```
(  
    -> Years: Longint  
    -> Months: Longint  
    -> Days: Longint  
    -> Hours: Longint  
    -> Minutes: Longint  
    -> Seconds: Longint  
)  
=> DTS Value: String[14]
```

| Parameter        | Type       | Description  |
|------------------|------------|--|
| <i>Years</i>     | Longint    | Years value  |
| <i>Months</i>    | Longint    | Months value                                       |
| <i>Days</i>      | Longint    | Days value   |
| <i>Hours</i>     | Longint    | Hours value  |
| <i>Minutes</i>   | Longint    | Minutes value                                      |
| <i>Seconds</i>   | Longint    | Seconds value                                      |
| <i>DTS Value</i> | String[14] | DTS value formed directly from supplied parameters |

The method *DTS\_Make\_from\_Values* creates directly a DTS value for the supplied incremental values.

*Years* is the numeric value to use for years. Values for *Years* are formatted to fit into four (4) bytes.

*Months* is the numeric value to use for months. Values for *Months* are formatted to fit into two (2) bytes.

*Days* is the numeric value to use for days. Values for *Days* are formatted to fit into two (2) bytes.

*Hours* is the numeric value to use for hours. Values for *Hours* are formatted to fit into two (2) bytes.

*Minutes* is the numeric value to use for minutes. Values for *Minutes* are formatted to fit into two (2) bytes.

*Seconds* is the numeric value to use for seconds. Values for *Seconds* are formatted to fit into two (2) bytes.

*DTS Value* is the DTS value created directly from the incrementally values.

The method *DTS\_Make\_from\_Values* does not perform any normalization upon the DTS value it creates. So, it is create a DTS value using this method which is used as a unique addend value for the method *DTS\_Add*.

#### Example:

All of the following conditionals will result to True:

```
DTS_Make_from_Values (1999;12;30;4;5;6)="19991230040506"
```

```
DTS_Make_from_Values (0;0;20;0;0;0)="00000020000000"  
0" ` 20 months
```

```
DTS_Make_from_Values (0;0;90;0;0;0)="00000090000000"  
0" ` 90 days
```

```
DTS_Make_from_Values (0;0;0;48;0;0)="00000000480000"  
0" ` 48 hours
```

```
DTS_Make_from_Values (0;0;0;0;0;90)="00000000000009"  
0" ` 90 seconds
```

**Note:** the method *DTS\_Make\_from\_Values* was added in BASH v1.4.7.



## DTS\_Subtract

*DTS\_Subtract* ( *Primary DTS Value* ; *Secondary DTS Value* ) =>  
*Differenced DTS Value*

```
DTS_Subtract  
(  
-> Primary DTS Value : String [14]  
-> Secondary DTS Value : String [14]  
)  
=> Differenced DTS Value : String [14]
```

| Parameter                | Type        | Description                                     |
|--------------------------|-------------|---|
| <i>Primary DTS Value</i> | String [14] | First DTS subtractive in transitive subtraction |

|                              |             |  |
|------------------------------|-------------|--|
| <i>Secondary DTS Value</i>   | String [14] | Second DTS subtractive in transitive subtraction |
| <i>Differenced DTS Value</i> | String [14] | Difference of DTS subtractives                   |

The method ***DTS\_Subtract*** will subtract two specified DTS values and return the difference in a DTS value. The time portion of the resulting DTS value will be normalized.

*Primary DTS Value* is the first DTS subtractive (the value to be subtracted from) in the transitive subtraction.

*Secondary DTS Value* is the second DTS subtractive (the value to be subtracted) in the transitive subtraction.

*Differenced DTS Value* is a well formed difference of *Primary DTS Value* and *Secondary DTS Value*. Only the time portion of *Differenced DTS Value* is normalized.

### Example:

The following table shows the values of two subtractives and the results which will be returned from the method ***DTS\_Subtract*** :

| 1st subtractive | 2nd subtractive | Difference     |
|-----------------|-----------------|----------------|
| 20001122040506  | 00000000010101  | 20001222030405 |
| 20001122040506  | 00010203000000  | 19990919040506 |
| 20001231040506  | 00000100000000  | 20001131040506 |
| 20000229040506  | 00010000000000  | 19990229040506 |
| 20001122040506  | 00000000060000  | 20001221220506 |

As can be seen by the above table, DTS values need not respect the rules of being well formed as date and time values often must in 4th Dimension. If a DTS value must be decremented by a certain amount, for instance by fourteen (14) days (i.e. two weeks), a single month, or merely twenty (20) hours, just it is as simple as creating a DTS value with only the amount to be incremented (use the method ***DTS\_Make\_from\_Values***, detailed above) and subtract it from the original DTS value by using the ***DTS\_Subtract*** method.

**Note:** the method *DTS\_Subtract* was added in BASH v1.5.4.



## **DTS\_Subtract\_Normalize**

*DTS\_Subtract\_Normalize* ( *Primary DTS Value* ; *Secondary DTS Value* ) => *Differenced DTS Value*

*DTS\_Subtract\_Normalize*  
(  
    -> *Primary DTS Value* : String [14]  
    -> *Secondary DTS Value* : String [14]  
)  
    => *Differenced DTS Value* : String [14]

| Parameter                    | Type        | Description                                      |
|------------------------------|-------------|--|
| <i>Primary DTS Value</i>     | String [14] | First DTS subtractive in transitive subtraction  |
| <i>Secondary DTS Value</i>   | String [14] | Second DTS subtractive in transitive subtraction |
| <i>Differenced DTS Value</i> | String [14] | Difference of DTS subtractives                   |

The method *DTS\_Subtract\_Normalize* will subtract two specified DTS values and return the difference in a DTS value. The date and time portions of the resulting DTS value will be normalized.

*Primary DTS Value* is the first DTS subtractive (the value to be subtracted from) in the transitive subtraction.

*Secondary DTS Value* is the second DTS subtractive (the value to be subtracted) in the transitive subtraction.

*Differenced DTS Value* is a well formed difference of *Primary DTS Value* and *Secondary DTS Value*. Both the date and time portions of *Differenced DTS Value* are normalized.

**Example:**

The following table shows the values of two subtractives and the results which will be returned from the method *DTS\_Subtract* :

| <u>1st subtractive</u> | <u>2nd subtractive</u> | <u>Difference</u> |
|------------------------|------------------------|-------------------|
| 20001122040506         | 00000000010101         | 20001222030405    |
| 20001122040506         | 00010203000000         | 19990919040506    |
| 20001231040506         | 00000100000000         | 20001201040506    |
| 20000229040506         | 00010000000000         | 19990301040506    |
| 20001122040506         | 00000000060000         | 20001221220506    |

As can be seen by the above table, DTS values need not respect the rules of being well formed as date and time values often must in 4th Dimension. If a DTS value must be decremented by a certain amount, for instance by fourteen (14) days (i.e. two weeks), a single month, or merely twenty (20) hours, just it is as simple as creating a DTS value with only the amount to be incremented (use the method *DTS\_Make\_from\_Values*, detailed above) and subtract it from the original DTS value by using the *DTS\_Subtract\_Normalize* method.

**Note:** the method *DTS\_Subtract\_Normalize* was added in BASH v1.5.4.

# ENV Module

The ENV module provides information about the 4D and application environment as it currently exists. The methods provide file names and paths to many of the items used within 4D development, as well as other basic information which may be variable over different instances of running 4D based applications.

**Note:** the ENV module was initially added in BASH v1.5.1.



## ENV\_ERROR

**ENV\_ERROR** (*BASH Error Number; Special Error Text; Calling Method Name*)

### ENV\_ERROR

```
(  
    -> BASH Error Number: Longint  
    -> Special Error Text: Text  
    -> Calling Method Name: Text  
)
```

| Parameter                  | Type    | Description   |
|----------------------------|---------|---|
| <i>BASH Error Number</i>   | Longint | Internal BASH error number                              |
| <i>Special Error Text</i>  | Text    | Special text to describe the exact error instance       |
| <i>Calling Method Name</i> | Text    | Name of the method that the error condition occurred in |

The method **ENV\_ERROR** acts as a callback method from within the ENV module for errors that may occur. Any time an error condition is detected within the ENV module, a call to the method **ENV\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method*

*Name* will always contain the name of the ARR method which call the **ENV\_ERROR** method.

The **ENV\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.

**Note:** the method **ENV\_ERROR** was added in BASH v1.5.4.



## **ENV\_Get\_4DXOS\_FolderPath**

**ENV\_Get\_4DXOS\_FolderPath** => *Folder Path*

**ENV\_Get\_4DXOS\_FolderPath**  
=> *Folder Path: Text*

| <b>Parameter</b>   | <b>Type</b> | <b>Description</b>                            |
|--------------------|-------------|---|
| <i>Folder Path</i> | Text        | Full path to 4DX folder within the current OS |

The method **ENV\_Get\_4DXOS\_FolderPath** will return the full folder path to the 4DX folder for the current platform within current system's preferences directory. This method will function correctly across platforms and in either single user or client/server environments.

This method will not confirm the actual existence of the returned full folder path. Rather, it just returns the full folder path to it for the current machine, whether it actually exists there or not.

*Folder Path* will be the full path to the 4DX folder for the current platform within the current system's preferences directory.

**Note:** the method **ENV\_Get\_4DXOS\_FolderPath** was added in BASH v1.5.3.



## ENV\_Get\_4DX\_FolderPath

**ENV\_Get\_4DX\_FolderPath** => *Folder Path*

**ENV\_Get\_4DX\_FolderPath**  
=> *Folder Path*: Text

| Parameter          | Type | Description  |
|--------------------|------|--|
| <i>Folder Path</i> | Text | Full path to 4DX folder next to the current structure document |

The method **ENV\_Get\_4DX\_Folder\_Path** will return the full folder path to the 4DX folder for the current platform within the structure's enclosing folder. This method will function correctly across platforms and in either single user or client/server environments. In client/server while on the client machine, the structure document's enclosing folder will be the folder containing the ".res" and ".rex" documents for the connected database.

This method will not confirm the actual existence of the returned full folder path. Rather, it just returns the full folder path to it for the current machine, whether it actually exists there or not.

*Folder Path* will be the full path to the 4DX folder for the current platform within the structure document's enclosing folder.

**Note:** the method **ENV\_Get\_4DX\_FolderPath** was added in BASH v1.5.3.



## ENV\_Get\_4DApplication\_FullPath

**ENV\_Get\_4DApplication\_FullPath** => *4D Application Path*

**ENV\_Get\_4DApplication\_FullPath**  
=> *4D Application Path*: Text

| Parameter | Type | Description |
|-----------|------|-------------|
|-----------|------|-------------|



|                            |             |  |
|----------------------------|-------------|--|
| <i>4D Application Path</i> | <b>Text</b> | <b>Full path to the currently running 4D application</b> |
|----------------------------|-------------|--|

The method *ENV\_Get\_4DApplication\_FullPath* returns the full path to the current 4D application. This is functionally equivalent to using the native **Application file** command within the 4D language, except no time slicing is given to the 4D application.

*4D Application Path* is the full path to the current 4D application which is running.

**Note:** the method *ENV\_Get\_4DApplication\_FullPath* was added in BASH v1.5.1.



## **ENV\_Get\_Application\_Name**

*ENV\_Get\_Application\_Name* => *Application Name*

*ENV\_Get\_Application\_Name*  
=> *Application Name:Text*

| <b>Parameter</b>        | <b>Type</b> | <b>Description</b>   |
|-------------------------|-------------|--|
| <i>Application Name</i> | <b>Text</b> | <b>Long name of the current application as stored in the resource fork of the current structure document</b> |

The method *ENV\_Get\_Application\_Name* returns the application name as stored in resource fork of the current structure document. The standard location to store the application name is in a resource of type 'STR#', ID 1, index 2, as defined by Apple developer documentation.

*Application Name* is the contents of the resource used for storing the application name within the current structure document.

**Note:** the method *ENV\_Get\_Application\_Name* was added in BASH v1.5.1.

---



## ENV\_Get\_Application\_Name\_Short

**ENV\_Get\_Application\_Name\_Short**=> *Application Short Name*

**ENV\_Get\_Application\_Name\_Short**  
=> *Application Short Name: Text*

| Parameter                     | Type | Description  |
|-------------------------------|------|--|
| <i>Application Short Name</i> | Text | Short name of the current application as stored in the resource fork of the current structure document |

The method **ENV\_Get\_Application\_Name\_Short** returns the application short name as stored in resource fork of the current structure document. The standard location to store the application short name is in a resource of type 'STR#', ID 1, index 1, as defined by Apple developer documentation.

*Application Short Name* is the contents of the resource used for storing the application short name within the current structure document.

**Note:** the method **ENV\_Get\_Application\_Name\_Short** was added in BASH v1.5.1.



---

## ENV\_Get\_Application\_Type

**ENV\_Get\_Application\_Type**=> *Application Indicator*

**ENV\_Get\_Application\_Type**  
=> *Application Indicator: Longint*

| Parameter                    | Type    | Description  |
|------------------------------|---------|--|
| <i>Application Indicator</i> | Longint | Application type of the currently running 4D application (application types are designated by the 4D constants <i>4D Environemnt</i> ) |

The method *ENV\_Get\_Application\_Type* returns the application type of the current 4D application. This is functionally equivalent to using the native **Application type** command within the 4D language, except no time slicing is given to the 4D application.

*Application Indicator* is the application type of the current 4D application which is running. Application type values are equivalent to the 4D constants within the *4D Environment* grouping.

**Note:** the method *ENV\_Get\_Application\_Type* was added in BASH v1.5.1.



## **ENV\_Get\_BASH\_HardName\_Long**

*ENV\_Get\_BASH\_HardName\_Long* => Long Hard Name

*ENV\_Get\_BASH\_HardName\_Long*  
=> Long Hard Name :Text

| Parameter      | Type | Description                                |
|----------------|------|--|
| Long Hard Name | Text | Full long hard name of Affix BASH document |

The method *ENV\_Get\_BASH\_HardName\_Long* returns the current full long hard name of the current Affix BASH document.

For information on the Affix BASH document, please read the section in this manual entitled **Affix BASH Document**.

For information on the hard file names, please read the section in the manual entitled **Hard File Names**.

*Long Hard Name* is the full long hard name of the current Affix BASH document.

**Note:** the method *ENV\_Get\_BASH\_HardName\_Long* was added in BASH v1.5.3.



## **ENV\_Get\_BASh\_HardName\_Short**

**ENV\_Get\_BASh\_HardName\_Short** => *Short Hard Name*

**ENV\_Get\_BASh\_HardName\_Short**  
=> *Short Hard Name* :Text

| Parameter              | Type | Description                                 |
|------------------------|------|---|
| <i>Short Hard Name</i> | Text | Full short hard name of Affix BASh document |

The method **ENV\_Get\_BASh\_HardName\_Short** returns the current full short hard name of the current Affix BASh document.

For information on the Affix BASh document, please read the section in this manual entitled **Affix BASh Document**.

For information on the hard file names, please read the section in the manual entitled **Hard File Names**.

*Short Hard Name* is the full short hard name of the current Affix BASh document.

**Note:** the method **ENV\_Get\_BASh\_HardName\_Short** was added in BASh v1.5.3.



## **ENV\_Get\_BASh\_RF\_FullPath**

**ENV\_Get\_BASh\_RF\_FullPath** => *Full Path*

**ENV\_Get\_BASh\_RF\_FullPath**  
=> *Full Path*:Text

| Parameter        | Type | Description   |
|------------------|------|---|
| <i>Full Path</i> | Text | Full path to the resource fork of the Affix BASh document |

The method *ENV\_Get\_BASH\_RF\_FullPath* returns the full path to the resource fork of the current Affix BASH document.

For information on the Affix BASH document, please read the section in this manual entitled **Affix BASH Document**.

*Full Path* is the full path to the resource fork of the current Affix BASH document. On a Macintosh, this is single Affix BASH document. On Windows, this is the resource fork document for the Affix BASH document (as opposed to the data fork).

**Note:** the method *ENV\_Get\_BASH\_RF\_FullPath* was added in BASH v1.5.3.



## **ENV\_Get\_DataFile\_FolderPath**

*ENV\_Get\_DataFile\_FolderPath* => *Folder Path*

*ENV\_Get\_DataFile\_FolderPath*  
=> *Folder Path*: Text

| Parameter          | Type | Description  |
|--------------------|------|--|
| <i>Folder Path</i> | Text | Full path to the folder containing the current data file |

The method *ENV\_Get\_DataFile\_FolderPath* returns the full path to the folder containing the current data file. This is functionally equivalent to using the native **Data file** command within the 4D language and extracting the file name, except no time slicing is given to the 4D application.

*Folder Path* is the full path to the folder containing the current data file which is in use.

**Note:** the method *ENV\_Get\_DataFile\_FolderPath* was added in BASH v1.5.3.



## ENV\_Get\_DataFile\_FullPath

**ENV\_Get\_DataFile\_FullPath**=> *Data File Path*

**ENV\_Get\_DataFile\_FullPath**  
=> *Data File Path*: Text

| Parameter             | Type | Description                        |
|-----------------------|------|------------------------------------|
| <i>Data File Path</i> | Text | Full path to the current date file |

The method **ENV\_Get\_DataFile\_FullPath** returns the full path to the current data file. This is functionally equivalent to using the native **Data file** command within the 4D language, except no time slicing is given to the 4D application.

*Data File Path* is the full path to the current data file which is in use.

**Note:** the method **ENV\_Get\_DataFile\_FullPath** was added in BASH v1.5.1.



## ENV\_Get\_DirectorySymbol

**ENV\_Get\_DirectorySymbol**=> *Directory Symbol*

**ENV\_Get\_DirectorySymbol**  
=> *Directory Symbol*: String1

| Parameter               | Type    | Description                                  |
|-------------------------|---------|--|
| <i>Directory Symbol</i> | String1 | Directory delimiter used on current platform |

The method **ENV\_Get\_DirectorySymbol** returns the character used as the delimiter between directory items on the current OS.

*Directory Symbol* is the characters used as the delimiter between directory items on the current OS. On Macintosh, this is the colon (":") and on Windows this is the back slash ("/").

Note: the method *ENV\_Get\_DirectorySymbol* was added in BASH v1.5.1.



## ENV\_Get\_DirectorySymbol\_by\_OS

*ENV\_Get\_DirectorySymbol\_by\_OS* ( Platform ) => Directory Symbol

*ENV\_Get\_DirectorySymbol\_by\_OS*

(  
    -> Platform : Longint  
)  
=> Directory Symbol: String1

| Parameter        | Type    | Description   |
|------------------|---------|---|
| Directory Symbol | String1 | Directory delimiter used on current platform  |
| Platform         | Longint | Platform indicator value (platform indicators are designated by the 4D constants <i>Platform Properties</i> ) |

The method *ENV\_Get\_DirectorySymbol\_by\_OS* returns the character used as the delimiter between directory items on the specified OS.

*Platform* is the platform indicator to get the directory symbol for. Platform indicators are designated by the 4D constants *Platform Properties* .

*Directory Symbol* is the characters used as the delimiter between directory items on the specified OS *Platform* . On Macintosh, this is the colon (":") and on Windows this is the back slash ("/").

Note: the method *ENV\_Get\_DirectorySymbol\_by\_OS* was added in BASH v1.5.3.



## ENV\_Get\_Platform

*ENV\_Get\_Platform* => Platform Indicator

*ENV\_Get\_Platform*

=> *Platform Indicator*: Longint

| Parameter                 | Type    | Description   |
|---------------------------|---------|---|
| <i>Platform Indicator</i> | Longint | Current platform indicator (platform indicators are designated by the 4D constants <i>Platform Properties</i> ) |

The method ***ENV\_Get\_Platform*** returns the platform indicator for the current platform being used. This is functionally equivalent to using the native **PLATFORM PROPERTIES** command within the 4D language, except no time slicing is given to the 4D application.

*Platform Indicator* is the value indicating the current platform which 4D is running under. *Platform Indicator* values are equivalent to the 4D constants within the *Platform Properties* grouping.

**Note:** the method ***ENV\_Get\_Platform*** was added in BASH v1.5.1.



## **ENV\_Get\_Structure\_DF\_FullPath**

***ENV\_Get\_Structure\_DF\_FullPath*** => *Full Path*

***ENV\_Get\_Structure\_DF\_FullPath***  
=> *Full Path*: Text

| Parameter        | Type | Description  |
|------------------|------|--|
| <i>Full Path</i> | Text | Full path of the data fork of the current structure file as it exists on the current machine |

The method ***ENV\_Get\_Structure\_DF\_FullPath*** returns the full path of the data fork of the structure file as it exists on the current machine.

When this method is called on Windows under single user 4D systems, it will return the correct full path, including the file extension, to the structure file as it currently exists. This will work even for merged 4D applications.



When this method is called on Macintosh under single user 4D systems, it will return the full path to the structure file as it currently exists. This path will be the same as the full path to the resource fork of the current structure file due to the nature of dual fork files under MacOS.

When this method is called under 4D Client, the full path is not a document that actually exists. This method considers the "RES" document the resource fork of the structure document and will return a full path to a corresponding data fork for the "RES" document if it were to exist.

*Full Path* is the full path of the data fork of the current structure on the current machine.

**Note:** the method *ENV\_Get\_Structure\_DF\_FullPath* was added in BASH v1.5.3.



## **ENV\_Get\_Structure\_FolderPath**

**ENV\_Get\_Structure\_FolderPath** => *Folder Path*

**ENV\_Get\_Structure\_FolderPath**  
=> *Folder Path: Text*

| <b>Parameter</b>   | <b>Type</b> | <b>Description</b>   |
|--------------------|-------------|--|
| <i>Folder Path</i> | Text        | Full path of the folder containing the current structure document on the current machine |

The method *ENV\_Get\_Structure\_FolderPath* returns the full path of the folder containing the current structure document on the current machine.

When this method is called under 4D Client, the folder containing the current structure document is the same as the folder containing the "RES" file within the 4D folder in the OS preferences.

*Full Path* is the full path to the folder containing the current structure document on the current machine.

**Note:** the method *ENV\_Get\_Structure\_FolderPath* was added in BASH v1.5.3.



## **ENV\_Get\_Structure\_RF\_FileName**

**ENV\_Get\_Structure\_RF\_FileName**=> *Structure Resource Fork File Name*

**ENV\_Get\_Structure\_RF\_FileName**

=> *Structure Resource Fork File Name: Text*

| <b>Parameter</b>                                 | <b>Type</b> | <b>Description</b>  |
|--|-------------|---|
| <i>Structure<br/>Resource Fork<br/>File Name</i> | <b>Text</b> | <b>File name of the resource fork of the current structure file as it exists on the current machine</b> |

The method *ENV\_Get\_Structure\_RF\_FileName* returns the file name of the resource fork of the structure file as it exists on the current machine.

When this method is called on Windows under single user 4D systems, it will return the correct file name, including the file extension, to the structure file as it currently exists. This will work even for merged 4D applications.

When this method is called on Macintosh under single user 4D systems, it will return the file name of the structure file as it currently exists. This file name will be the same as the file name of the data fork of the current structure file due to the nature of dual fork files under MacOS.

When this method is called under 4D Client, the file name will be correct file name of the "RES" file as stored in the 4D folder. The "RES" file is just a copy of the resource fork of the current structure file, maintained automatically by 4D Client when running in client/server applications. Keep in mind, though, that resources modified in the "RES" file on 4D Client are *not* updated to

the structure file on the server. In these cases, the resource fork on the server should be edited directly and flagged to be updated by the clients the next time they connect.

*Structure Resource Fork File Name* is the file name of the resource fork of the current structure on the current machine.

**Note:** the method *ENV\_Get\_Structure\_RF\_FileName* was added in BASH v1.5.1.



## **ENV\_Get\_Structure\_RF\_FullPath**

**ENV\_Get\_Structure\_RF\_FullPath** => *Structure Resource Fork Full Path*

**ENV\_Get\_Structure\_RF\_FullPath**

=> *Structure Resource Fork Full Path: Text*

| <b>Parameter</b>                         | <b>Type</b> | <b>Description</b>   |
|--|-------------|--|
| <i>Structure Resource Fork Full Path</i> | Text        | Full path of the resource fork of the current structure file as it exists on the current machine |

The method *ENV\_Get\_Structure\_RF\_FullPath* returns the full path of the resource fork of the structure file as it exists on the current machine.

When this method is called on Windows under single user 4D systems, it will return the correct full path, including the file extension, to the structure file as it currently exists. This will work even for merged 4D applications.

When this method is called on Macintosh under single user 4D systems, it will return the full path to the structure file as it currently exists. This path will be the same as the full path to the data fork of the current structure file due to the nature of dual fork files under MacOS.

When this method is called under 4D Client, the full path will be correct path of the "RES" file as stored in the 4D folder. The "RES" file is just a copy of the resource fork of the current structure file, maintained automatically by 4D Client when running in client/server applications. Keep in mind, though, that resources modified in the "RES" file on 4D Client are *not* updated to the structure file on the server. In these cases, the resource fork on the server should be edited directly and flagged to be updated by the clients the next time they connect.

*Structure Resource Fork Full Path* is the full path of the resource fork of the current structure on the current machine.

**Note:** the method *ENV\_Get\_Structure\_RF\_FullPath* was added in BASH v1.5.1.



## ENV\_q\_Macintosh

*ENV\_q\_Macintosh* => *Macintosh Flag*

*ENV\_q\_Macintosh*

=> *Macintosh Flag*: Boolean

| Parameter             | Type    | Description                                |
|-----------------------|---------|--|
| <i>Macintosh Flag</i> | Boolean | Flag for current machine running Macintosh |

The method *ENV\_q\_Macintosh* returns a flag for whether the current machine is running under type of Macintosh OS, including Sytem 7, MacOS 8, or MacOS 9.

*Macintosh Flag* is the boolean value for whether the current machine is running under Windows.

**Note:** the method *ENV\_q\_Macintosh* was added in BASH v1.5.3.



## ENV\_q\_Windows

**ENV\_q\_Windows** => Windows Flag

**ENV\_q\_Windows**  
=> Windows Flag: Boolean

| Parameter    | Type    | Description                              |
|--------------|---------|--|
| Windows Flag | Boolean | Flag for current machine running Windows |

The method **ENV\_q\_Windows** returns a flag for whether the current machine is running under any type of Windows OS, including Windows 95/98/2000 and Windows NT.

*Windows Flag* is the boolean value for whether the current machine is running under Windows.

**Note:** the method **ENV\_q\_Windows** was added in BASH v1.5.1.



## **ENV\_Set\_FlushKey**

**ENV\_Set\_FlushKey** ( ASCII Value )

**ENV\_Set\_FlushKey**  
(  
    -> ASCII Value : Longint  
)

| Parameter   | Type    | Description  |
|-------------|---------|--|
| ASCII Value | Longint | ASCII Value to set for the automatic Flush Buffers functionality within 4D |

The method **ENV\_Set\_FlushKey** will set the keyboard equivalent value for the current Flush Buffers functionality available within 4D.

The value is set directly into the resource fork of the current 4D application. This includes 4D, 4D Server, 4D Client, 4D Runtime, and structure documents which have been merged with 4D Engine. This method will set the

internal Flush Buffer keyboard equivalent for all of these applications.

The changing of the Flush Buffers keyboard equivalent value will not affect the current instance of 4D which is running. All instances of the 4D product line load this value from the resource fork immediately upon launching. Changing this value in the resource fork from code within the structure will not be effective then until the next launching of the same 4D application.

*ASCII Value* is the ASCII value of the character to use as the keyboard equivalent for the internal Flush Buffers functionality within 4D.

**Note:** the method *ENV\_Set\_FlushKey* was added in BASH v1.5.3.

## FILE Module

The FILE modules deals with path and file names directly within the operating system (OS). The current functionality available within the FILE module is fairly limited. But, with future versions of the BASH component, enhancements to the FILE module will be made available.

### Hard File Names

Hard file names are a very old convention originally used on the Macintosh. Hard file names provide a means for specific documents to be identified exactly even if the actual document names have been changed.

Essentially, hard file names are string values which are stored in a particular location in the resource fork of a document.

Two different hard file names exist: short and long. The short hard file name is just the name to be used for identification purposes for the document. The long hard file name is the same as the short hard file name except the name also contains the current version number of the document.

For instance, the Affix BASH document contains the resources for hard file names. The short hard file name of the Affix BASH document is "Affix\_BASH". The long hard file name of the Affix BASH document is "Affix\_BASH\_v1.5.9". These hard file names stored in the resource fork of the Affix BASH document provide a means for the methods within the BASH component to identify the Affix BASH document within the 4DX folders even if the document has been renamed. By using the commands within the FILE module for hard file names, the same functionality can be built very easily within your own 4D projects for documents which must be managed.

The actual location which the hard file names are stored is as follows: 'STR#', ID 1. Short hard file names are stored in index 1. Long hard file names are stored in index 2.

**Note:** the FILE module was initially added in BASH v1.5.1.



## **FILE\_Convert\_to\_ResFork\_Windows**

**FILE\_Convert\_to\_ResForm\_Windows**( *Data Fork Full Path*) => *Resource Fork Full Path*

**FILE\_Convert\_to\_ResForm\_Windows**  
(  
    -> *Data Fork Full Path: Text*  
)  
=> *Resource Fork Full Path: Text*

| <b>Parameter</b>               | <b>Type</b> | <b>Description</b>  |
|--------------------------------|-------------|---|
| <i>Data Fork Full Path</i>     | <b>Text</b> | Full path to data fork of a document                                      |
| <i>Resource Fork Full Path</i> | <b>Text</b> | Full path to the resource fork of the <i>Data Fork Full Path</i> document |

The method **FILE\_Convert\_to\_ResFork\_Windows** will convert a full path, relative path, or file name for the data fork of a file on Windows to the instead be to the resource fork on Windows. This will work for both plugins, applications, structure, and data documents used commonly in the 4D environment.

This method will check the *Data Fork Full Path* parameter to see if the file pointed to a 4D data file. If so, then the file extension is changed to "4DR". If the *Data Fork Full Path* does not name a 4D data file, then the extension is changed to "RSR". No confirmation is done as to the well form nature of the *Data Fork Full Path* parameter.



*Data Fork Full Path* is a valid full path, relative path, or file name for Windows.

*Resource Fork Full Path* is the *Data Fork Full Path* value modified to be a valid resource file name on Windows. *Resource Fork Full Path* is merely a string substitution done on the last four bytes of *Data Fork Full Path*.

**Note:** the method *FILE\_Convert\_to\_ResFork\_Windows* was added in BASH v1.5.1.



## **FILE\_Create\_Document**

**FILE\_Create\_Document** ( *Document Full Path* ; *Document Type* ) =>  
*Document Reference*

**FILE\_Create\_Document**  
(  
    -> *Document Full Path* : **Text**  
    -> *Document Type* : **Longint**  
)  
=> *Document Reference*: **Time**

| <b>Parameter</b>          | <b>Type</b>    | <b>Description</b>                 |
|---------------------------|----------------|------------------------------------|
| <i>Document Full Path</i> | <b>Text</b>    | Full path to document to create    |
| <i>Document Type</i>      | <b>Longint</b> | Document type to create            |
| <i>Document Reference</i> | <b>Time</b>    | File reference to document created |

The method *FILE\_Create\_Document* will create a new document at a specified location of a specified type and return the document reference to its data fork.

If the document specified in *Document Full Path* already exists then *FILE\_Create\_Document* will generate an error and return NULL in *Document Reference*. If *Document Type* is NULL then the document will be created using the default file type ('TEXT' on Macintosh and ".txt" on Windows).

*Document Full Path* is the full path to the document to create.

*Document Type* is the type of document to be created. If *Document Type* is NULL (zero, 0) then the document will be created using the default document type ('TEXT' on Macintosh and ".txt" on Windows).

*Document Reference* is the document reference to the new document created. This reference is the file reference to the data fork of the new document. If there is an error creating the new document then *Document Reference* will be NULL.

**Note:** the method *FILE\_Create\_Document* was added in BASH v1.5.3.



## **FILE\_Create\_Folder**

**FILE\_Create\_Folder** ( *Folder Full Path* ) => Success

**FILE\_Create\_Folder**  
(  
    -> *Folder Full Path* : Text  
)  
=> Success : Longint

| Parameter               | Type    | Description  |
|-------------------------|---------|--|
| <i>Folder Full Path</i> | Text    | Full path to folder to create  |
| Success                 | Longint | Success indicator for creating folder specified in <i>Folder Full Path</i> |

The method *FILE\_Create\_Folder* will create a specified folder.

If the folder specified in *Folder Full Path* already exists then this method will generate an error and will indicate failure in the *Success* indicator value returned.

*Folder Full Path* is the full path to the new folder to create.

*Success* is the indicator value for whether the new folder was successfully created in this method. *Success* will be set to one (1) if the new folder was successfully created. If the folder already exists or failed to be created then *Success* will be set to zero (0).

**Note:** the method *FILE\_Create\_Folder* was added in BASH v1.5.3.



## **FILE\_Create\_FullPath\_Document**

**FILE\_Create\_FullPath\_Document** ( *Full Document Path* ) => *Success Status*

**FILE\_Create\_FullPath\_Document**

```
(  
    -> Full Document Path : Text  
)  
=> Success Status : Longint
```

| Parameter                 | Type    | Description  |
|---------------------------|---------|--|
| <i>Full Document Path</i> | Text    | Full path to document and folder hierarchy to create               |
| <i>Success Status</i>     | Longint | Status code for successfully created document and folder hierarchy |

The method *FILE\_Create\_FullPath\_Document* will create a document in a specified location in the directory hierarchy with the specified name.

If any folders in the directory hierarchy specified do not exist, they will be created. If the document does not already exist, it will be created. If the document specified already exists, it will remain unmodified *FILE\_Create\_FullPath\_Document* .

If *FILE\_Create\_FullPath\_Document* creates the document, the document type will be the default document type assigned by the native 4th Dimension command **Create Document**.

Often, *FILE\_Create\_FullPath\_Document* is used to confirm the existence of a particular document in a

specific location. And, to create the document with the full accompanying folder hierarchy, in the event that it is needed.

*Full Document Path* is the full path to the document to confirm existence of and possibly create.

*Success Status* is the status code returned by this method. The following table lists the values which can be returned in *Success Status* :

| Value | Meaning                       |
|-------|-------------------------------|
| 2     | document created successfully |
| 1     | document already exists       |
| 0     | document does not exist       |
| - 1   | not a document                |
| - 2   | error creating folder path    |
| - 3   | error creating document       |

**Note:** the method *FILE\_Create\_FullPath\_Document* was added in BASH v1.5.4.



## **FILE\_Create\_FullPath\_Folder**

***FILE\_Create\_FullPath\_Folder*** ( *Full Folder Path* ) => *Success Status*

***FILE\_Create\_FullPath\_Folder***  
(  
    -> *Full Folder Path* : **Text**  
)  
    => *Success Status* : **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>                                    |
|-------------------------|----------------|---|
| <i>Full Folder Path</i> | <b>Text</b>    | Full path to folder hierarchy to create               |
| <i>Success Status</i>   | <b>Longint</b> | Status code for successfully created folder hierarchy |

The method *FILE\_Create\_FullPath\_Folder* will create a specified directory hierarchy. If any folders in the directory hierarchy specified do not exist, they will be created.

Often, *FILE\_Create\_FullPath\_Folder* is used to confirm the existence of a particular folder hierarchy. And, to create the folder hierarchy, in the event that it is needed.

*Full Folder Path* is the full path to the folder hierarchy to confirm existence of and possibly create.

*Success Status* is the status code returned by this method. The following table lists the values which can be returned in *Success Status* :

| Value | Meaning                                   |
|-------|---|
| 2     | document folder hierarchy successfully    |
| 1     | folder hierarchy already exists           |
| 0     | folder hierarchy does not exist           |
| -1    | not a valid folder hierarchy              |
| -2    | volume does not exist                     |
| -3    | error creating folder in folder hierarchy |

**Note:** the method *FILE\_Create\_FullPath\_Folder* was added in BASH v1.5.4.



## FILE\_ERROR

**FILE\_ERROR** ( *BASH Error Number*; *Special Error Text*; *Calling Method Name* )

### FILE\_ERROR

```
(
    -> BASH Error Number: Longint
    -> Special Error Text: Text
    -> Calling Method Name: Text
)
```

| Parameter                  | Type    | Description   |
|----------------------------|---------|---|
| <i>BASH Error Number</i>   | Longint | Internal BASH error number                              |
| <i>Special Error Text</i>  | Text    | Special text to describe the exact error instance       |
| <i>Calling Method Name</i> | Text    | Name of the method that the error condition occurred in |

The method **FILE\_ERROR** acts as a callback method from within the FILE module for errors that may occur. Any time an error condition is detected within the FILE module, a call to the method **FILE\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the ARR method which call the **FILE\_ERROR** method.

The **FILE\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.

**Note:** the method **FILE\_ERROR** was added in BASH v1.5.3.



## **FILE\_Find\_FileName\_Hard\_Long**

**FILE\_Find\_FileName\_Hard\_Long** ( *Long Hard Name ; Full Path* ) =>  
*Matching File Name*

**FILE\_Find\_FileName\_Hard\_Long**  
(  
    -> *Long Hard Name* : **Text**  
    -> *Full Path* : **Text**  
)  
=> *Matching File Name* : **Text**

| <b>Parameter</b>          | <b>Type</b> | <b>Description</b>   |
|---------------------------|-------------|--|
| <i>Long Hard Name</i>     | <b>Text</b> | Long hard file name to match   |
| <i>Full Path</i>          | <b>Text</b> | Full path to folder to scan for <i>Long Hard Name</i>                        |
| <i>Matching File Name</i> | <b>Text</b> | File name of document within <i>Full Path</i> matching <i>Long Hard Name</i> |

The method *FILE\_Find\_FileName\_Hard\_Long* will return the file name of the first document within a specified folder matching a specified long hard file name.

*Long Hard Name* is the long hard file name to match.

*Full Path* is the full folder path to a folder to scan the contents of for *Long Hard Name*. Only the documents directly within the *Full Path* directory will be scanned. Documents contained within directories within the *Full Path* folder will not be scanned.

*Matching File Name* is the name of the document matching *Long Hard Name* within the folder *Full Path*. If no documents within *Full Path* match *Long Hard Name* then *Matching File Name* will be NULL.

**Note:** the method *FILE\_Find\_FileName\_Hard\_Long* was added in BASH v1.5.3.



## **FILE\_Find\_FileName\_Hard\_Short**

**FILE\_Find\_FileName\_Hard\_Short** ( *Short Hard Name* ; *Full Path* ) =>  
*Matching File Name*

**FILE\_Find\_FileName\_Hard\_Short**  
(  
    -> *Short Hard Name* : **Text**  
    -> *Full Path* : **Text**  
)  
=> *Matching File Name* : **Text**

| <b>Parameter</b>          | <b>Type</b> | <b>Description</b>  |
|---------------------------|-------------|---|
| <i>Short Hard Name</i>    | <b>Text</b> | Short hard file name to match   |
| <i>Full Path</i>          | <b>Text</b> | Full path to folder to scan for <i>Short Hard Name</i>                        |
| <i>Matching File Name</i> | <b>Text</b> | File name of document within <i>Full Path</i> matching <i>Short Hard Name</i> |

The method *FILE\_Find\_FileName\_Hard\_Short* will return the file name of the first document within a

specified folder matching a specified short hard file name.

*Short Hard Name* is the short hard file name to match.

*Full Path* is the full folder path to a folder to scan the contents of for *Short Hard Name*. Only the documents directly within the *Full Path* directory will be scanned. Documents contained within directories within the *Full Path* folder will not be scanned.

*Matching File Name* is the name of the document matching *Short Hard Name* within the folder *Full Path*. If no documents within *Full Path* match *Short Hard Name* then *Matching File Name* will be NULL.

**Note:** the method *FILE\_Find\_FileName\_Hard\_Short* was added in BASH v1.5.3.



## **FILE\_FullPath\_to\_FileName**

**FILE\_FullPath\_to\_FileName**( *Full Path* ) => *File Name*

**FILE\_FullPath\_to\_FileName**  
(  
    -> *Full Path*: Text  
)  
    => *File Name*: Text

| Parameter        | Type | Description   |
|------------------|------|---|
| <i>Full Path</i> | Text | Full path to a document                             |
| <i>File Name</i> | Text | File name of document specified in <i>Full Path</i> |

The method *FILE\_FullPath\_to\_FileName* will take a full or relative path and return the filename portion. The currently directory delimiter value is respected so that full cross-platform compatibility is available within this method.

*Full Path* is the full or relative path to a file on the current platform.



*File Name* is the file name portion of *Full Path* as it would exist on the current platform.

**Note:** the method *FILE\_FullPath\_to\_FileName* was added in BASH v1.5.1.



## **FILE\_Get\_Document\_List**

**FILE\_Get\_Document\_List** ( *Folder Full Path* ; *Referenced Document Names* ) => *Document Count*

**FILE\_Get\_Document\_List**  
(  
    -> *Folder Full Path* : **Text**  
    -> *Referenced Document Names* : **Pointer**  
)  
    => *Document Count*: **Longint**

| <b>Parameter</b>                 | <b>Type</b>    | <b>Description</b>   |
|----------------------------------|----------------|--|
| <i>Folder Full Path</i>          | <b>Text</b>    | Full path to folder  |
| <i>Referenced Document Names</i> | <b>Pointer</b> | Pointer to text array to hold document names                     |
| <i>Document Count</i>            | <b>Longint</b> | Number of documents returned in <i>Referenced Document Names</i> |

The method *FILE\_Get\_Document\_List* returns the number of documents and document names within a specified directory.

*Folder Full Path* is the full path to a directory to get the directory listing of documents from.

*Referenced Document Names* is a pointer to a text array which will hold the names of all of the documents within *Folder Full Path*.

*Document Count* is the number of documents contained within *Folder Full Path*. This will be the same number of elements in *Referenced Document Names* after this method is called.

Note: the method *FILE\_Get\_Document\_List* was added in BASH v1.5.3.



## **FILE\_Get\_Path\_Parent**

**FILE\_Get\_Path\_Parent** ( *Full Path* ; *Platform* ) => *Full Parent Path*

**FILE\_Get\_Path\_Parent**

```
(  
    -> Full Path : Text  
    -> Platform : Longint  
)  
=> Full Parent Path: Text
```

| Parameter               | Type    | Description  |
|-------------------------|---------|--|
| <i>Full Path</i>        | Text    | Full path to folder or document  |
| <i>Platform</i>         | Longint | Platform indicator value which <i>Full Path</i> is valid upon (platform indicators are designated by the 4D constants <i>Platform Properties</i> ) |
| <i>Full Parent Path</i> | Text    | Full path to parent of <i>Full Path</i>  |

The method *FILE\_Get\_Path\_Parent* will return the full path to the enclosing directory for a specified full path to a document or directory. This method will operate correctly for paths on either Macintosh or Windows and it will automatically detect whether the full path specified is to a folder or a document.

*Full Path* is the full path to either a document or directory on either Macintosh or Windows.

*Platform* is the platform indicator value which *Full Path* is valid upon. Platform indicators are designated by the 4D constants *Platform Properties* .

*Full Parent Path* returns the full path to the parent directory of *Full Path*. *Full Parent Path* can be either the full path to the directory containing the directory specified by *Full Path* or *Full Parent Path* can be the full path to the directory containing the document specified by *Full Path*.

Note: the method *FILE\_Get\_Path\_Parent* was added in BASH v1.5.3.



## **FILE\_Get\_Volumes\_Names**

**FILE\_Get\_Volumes\_Names** ( *Referenced Text Array* )

**FILE\_Get\_Volumes\_Names**

(  
    -> *Referenced Text Array* : **Pointer**  
)

| Parameter                    | Type           | Description   |
|------------------------------|----------------|---|
| <i>Referenced Text Array</i> | <b>Pointer</b> | Referenced array to contain list of volumes available on the current, local machine |

The method *FILE\_Get\_Volumes\_Names* will return the list of volumes available on the current, local machine.

*FILE\_Get\_Volumes\_Names* acts similar to the native 4th Dimension command **VOLUME LIST**, with the exception that both platforms will return volumes names as fully qualified directory paths, including the trailing item delimiter. This correction allows for completely seamless integration of this command across platforms in 4D.

*Referenced Text Array* is a referenced text or string array which is to contain the list of volumes available on the current, local machine.

Note: the method *FILE\_Get\_Volumes\_Names* was added in BASH v1.5.4.



## **FILE\_qi\_Document\_Exists**

**FILE\_qi\_Document\_Exists** ( *Full Document Path* ) => *Exists*

## ***FILE\_qi\_Document\_Exists***

```
(  
    -> Full Document Path : Text  
)  
=> Exists: Longint
```

| Parameter                 | Type    | Description                                  |
|---------------------------|---------|--|
| <i>Full Document Path</i> | Text    | Full path to document to check for existence |
| <i>Exists</i>             | Longint | Existence indicator value                    |

The method ***FILE\_qi\_Document\_Exists*** will return an indicator value for whether a specified document at a specified location actually exists.

*Full Document Path* is the full path to a document on the current machine.

*Exists* is an indicator value for whether the document *Full Document Path* exists. If *Exists* is one (1) then the document *Full Document Path* actually exists on the current machine. If *Exists* is zero (0) then the document *Full Document Path* does not exist on the current machine.

**Note:** the method ***FILE\_qi\_Document\_Exists*** was added in BASH v1.5.3.



## ***FILE\_qi\_Folder\_Exists***

***FILE\_qi\_Folder\_Exists*** ( *Full Folder Path* ) => *Exists*

### ***FILE\_qi\_Folder\_Exists***

```
(  
    -> Full Folder Path : Text  
)  
=> Exists: Longint
```

| Parameter               | Type    | Description                                   |
|-------------------------|---------|---|
| <i>Full Folder Path</i> | Text    | Full path to directory to check for existence |
| <i>Exists</i>           | Longint | Existence indicator value                     |

The method *FILE\_qi\_Folder\_Exists* will return an indicator value for whether a specified directory at a specified location actually exists.

*Full Folder Path* is the full path to a directory on the current machine.

*Exists* is an indicator value for whether the directory *Full Folder Path* exists. If *Exists* is one (1) then the directory *Full Folder Path* actually exists on the current machine. If *Exists* is zero (0) then the directory *Full Folder Path* does not exist on the current machine.

**Note:** the method *FILE\_qi\_Folder\_Exists* was added in BASH v1.5.3.



## **FILE\_qi\_Volume\_Exists**

***FILE\_qi\_Volume\_Exists*** (*Named Volume* ) => *Exists*

***FILE\_qi\_Volume\_Exists***

```
(  
    -> Named Volume : Text  
)  
=> Exists : Longint
```

| Parameter           | Type    | Description                               |
|---------------------|---------|---|
| <i>Named Volume</i> | Text    | Volume name to confirm existence of       |
| <i>Exists</i>       | Longint | qi for whether volume named exists or not |

The method *FILE\_qi\_Volume\_Exists* will confirm whether a named volume actually exists on the current, local machine.

*Named Volume* is a named volume to check for existence on the current, local machine.

*Exists* is qi for whether *Named Volume* exists on the current local machine. If *Named Volume* exists, *Exists*

will be set to one (1); if the named volume does not exist, *Exists* will be set to zero (0).

**Note:** the method *FILE\_qi\_Volume\_Exists* was added in BASH v1.5.4.

# INIT Module

The INIT module is the first module which needs to be dealt with in the BASH component. At this time, it consists of only a single routine. But, this single routine provides initialization for all of the modules within the BASH component.

It is **strongly** recommended that all initialization be done early in the **On Startup** database method.

And, it is also strongly recommended to not consider any of the methods in the INIT module as reentrant during any single use of the application without it being clearly stated in this documentation.

**Note:** the INIT module was added in BASH v1.5.4.



## INIT\_BASH

### *INIT\_BASH*

### *INIT\_BASH*

| Parameter | Type | Description |
|-----------|------|-------------|
| (none)    | n/a  | n/a         |

The method *INIT\_BASH* will initialize the whole BASH component.

Before any of the methods within the BASH component can function, *INIT\_BASH* should be called. It is best to call *INIT\_BASH* early in the **On Startup** database method

There is no need to call *INIT\_BASH* twice during the operation of the database. And, it is actually discouraged to call the method repeatedly during use of the application.

There are no parameters or returned values to *INIT\_BASH*.

**Note:** the method *INIT\_BASH* was added in BASH v1.5.4.



## NULL Module

The NULL module is just a feeble attempt to make up for 4th Dimension lacking support for actual NULL/Nil values. At its core, the NULL module contains variables of each type that contain empty values (zero, empty string, zero-byte picture and BLOB, Nil pointer, etc.). Using these values, the methods within the NULL module make it easier to clear the values in a set of variables, test whether a value is NULL, and more. The functionality available in the NULL module is very simplistic; its power comes from consistent use of it throughout your code.

For the sake of reference, the following is a listing of the actual NULL variables, their types, and their values:

| Variable | Type       | Value               |
|----------|------------|---------------------|
| zNULL    | BLOB       | Blob Size is 0      |
| qNULL    | Boolean    | False               |
| dNULL    | Date       | !00/00/00!          |
| isNULL   | Integer    | 0                   |
| iNULL    | LongInt    | 0                   |
| yNULL    | Picture    | (*0, empty Picture) |
| pNULL    | Pointer    | Nil                 |
| rNULL    | Real       | 0                   |
| xNULL    | Text       | ""                  |
| tNULL    | Time       | †00:00:00†          |
| dt\$NULL | String, 14 | "0000000000000000"  |

Under **no** circumstances should you **ever** set values into these variables. They are listed here solely for your convenience and reference purposes. Their values can be assigned to other variables, but no value should ever be set into these NULL variables.

The initial assignment of the empty values to these variables is handled internally within the NULL module. Assigning different values to any of these variables will result in erroneous operation of the code with the BASH component.



## NULL\_Dereference\_by\_Type

**NULL\_Dereferenced\_by\_Type** ( Variable Type) => Referenced NULL Variable

**NULL\_Dereference\_by\_Type**

(  
    -> Variable Type: Longint  
)  
=> Referenced DSS Variable: Pointer

| Parameter                | Type    | Description  |
|--------------------------|---------|--|
| Variable Type            | Longint | Type of NULL variable reference wanted (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |
| Referenced NULL Variable | Pointer | Reference to NULL variable matching type of Variable Type  |

The method **NULL\_Reference\_by\_Type** returns a reference to one of the NULL variables matching the variable type specified.

### Example:

It is common to use such a reference as an empty value within a method. For instance, consider the following code fragment:

```
C_TEXT($xMyText;$1)
$xMyText:=$1
C_LONGINT($iErrorCode)
$iErrorCode:=MyMethod ($xMyText;"";"";69)
```

It is not exactly clear what is being done or even how many parameters are being passed to *MyMethod* (well, for us old people that have poor eyesight). The following code fragment is much easier to read and understand:

```
C_TEXT($xMyText;$1)
$xMyText:=$1
C_LONGINT($iErrorCode)
C_TEXT($xNoValue)
$xNoValue:=NULL_Dereference_by_Type (Is Text) ->
$iErrorCode:=MyMethod ($xMyText;$xNoValue;$xNoValue;69)
```



## NULL\_ERROR

**NULL\_ERROR** (*BASH Error Number*; *Special Error Text*; *Calling Method Name*)

### NULL\_ERROR

(  
    -> *BASH Error Number*: **Longint**  
    -> *Special Error Text*: **Text**  
    -> *Calling Method Name*: **Text**  
)

| Parameter                  | Type           | Description   |
|----------------------------|----------------|---|
| <i>BASH Error Number</i>   | <b>Longint</b> | Internal NULL error number                              |
| <i>Special Error Text</i>  | <b>Text</b>    | Special text to describe the exact error instance       |
| <i>Calling Method Name</i> | <b>Text</b>    | Name of the method that the error condition occurred in |

The method **NULL\_ERROR** acts as a callback method from within the DSS module for errors that may occur. Any time an error condition is detected within the NULL module, a call to the method **NULL\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the DSS method which call the **NULL\_ERROR** method.

The **NULL\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed



## NULL\_Get\_DTS

**NULL\_Get\_DTS** => NULL DTS Value

**NULL\_Get\_DTS**

=> NULL DTS Value: String [14]

| Parameter      | Type       | Description                                       |
|----------------|------------|---|
| NULL DTS Value | String[14] | Returns NULL DTS value, which is "00000000000000" |

The method **NULL\_Get\_DTS** returns a NULL DTS value. That is, the value returned from **NULL\_Get\_DTS** is equal to "00000000000000", or 14 zeros ("0"\*14).

See the DTS library for more information on DTS values.

**Note:** the method **NULL\_Get\_DTS** was added in BASH v1.4.7.



## NULL\_Get\_Pointer

**NULL\_Get\_Pointer** => nil pointer

**NULL\_Get\_Pointer**

=> nil pointer: Pointer

| Parameter   | Type    | Description           |
|-------------|---------|-----------------------|
| nil pointer | Pointer | Returns a Nil pointer |

The method **NULL\_Get\_Pointer** returns a Nil pointer. That is, the pointer returned from the method **NULL\_Get\_Pointer** will evaluate in the Nil command in 4th Dimension as TRUE.

### Example:

Due to an *anomaly* in compiled and merged 4th Dimension for Windows applications, assigning a dereferenced reference to a Nil reference will crash the merged application. In other words, the following code fragment

will fail horribly as a compiled and merged Windows application:

```
C_POINTER($pClearThisVar)
$pClearThisVar:=NULL_Dereference_by_Type (Is Pointer)
->
```

To get around this slight aberration in 4D, the following code fragment should be used instead:

```
C_POINTER($pClearThisVar)
$pClearThisVar:=NULL_Get_Pointer
```

Hopefully, a future version of 4th Dimension will make this unnecessary, though for now it is needed to consistently utilize the NULL module of code.



## NULL\_Set\_Variables

**NULL\_Set\_Variables** ( *Referenced Variable* {; ... } )

**NULL\_Set\_Variables**

```
(
    -> Referenced Variable: Pointer
    { -> Referenced Variable: Pointer }
)
```

| Parameter                  | Type    | Description  |
|----------------------------|---------|--|
| <i>Referenced Variable</i> | Pointer | Reference to variable(s) to clear (set to NULL values) |

The method **NULL\_Set\_Variables** will clear between one (1) and sixteen (16) referenced variables, setting their values to NULL.

This makes the initialization and clearing of variables extremely simple, saving many lines of code. For instance, consider the following code fragment:

```
SET BLOB SIZE (zMyBlob;0)
xMyText:=""
yMyPicture:=yMyPicture*0
```

This can quickly become cumbersome. Instead, a single line of code can be written:

```
NULL_Set_Variables (->zMyBlob; ->xMyText; ->yMyPicture)
```

This single line of code is much more compact and easier to read. As well, it provides a good reminder to always be tidy in the management of your memory as used by variables in your 4th Dimension applications.

# NVP Module

The NVP module is available for handling named value pairs. The methods available in the NVP module provide easy access to packing, unpacking, and extracting values from NVP stacks and text variables.

An NVP stack is a pair of text arrays which manage named data values. One array holds the names (keys) of the values. The other array contains the values associated with each named element. A NVP stack must always be well form, meaning that both arrays must always contain the same number of elements.

The routines available in the NVP modules provide a simple means for NVP stacks to be formatted into a single text variable. And, there is even a method to extract a named value from a formatted NVP stack stored in a text variable.

**Note:** the NVP module was initially added in BASH v1.5.1.



## NVP\_ERROR

**NVP\_ERROR** (*BASH Error Number; Special Error Text; Calling Method Name*)

### NVP\_ERROR

```
(  
    -> BASH Error Number: Longint  
    -> Special Error Text: Text  
    -> Calling Method Name: Text  
)
```

| Parameter          | Type    | Description                                       |
|--------------------|---------|---|
| BASH Error Number  | Longint | Internal NULL error number                        |
| Special Error Text | Text    | Special text to describe the exact error instance |

| Calling Method Name | Text | Name of the method that the error condition occurred in |
|---------------------|------|---|
|---------------------|------|---|

The method ***NVP\_ERROR*** acts as a callback method from within the NVP module for errors that may occur. Any time an error condition is detected within the NVP module, a call to the method ***NVP\_ERROR*** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the DSS method which call the ***NVP\_ERROR*** method.

The ***NVP\_ERROR*** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed

**Note:** the method ***NVP\_ERROR*** was added in BASH v1.5.1.



## **NVP\_Extract\_Values\_by\_Name\_s**

***NVP\_Extract\_Values\_by\_Name\_s*** (*NVP Name*; *Referenced Names Array*; *Referenced Values Array* ) => *NVP Value*

***NVP\_Extract\_Values\_by\_Name\_s***

```
(
    -> NVP Name: Text
    -> Referenced Names Array: Pointer
    -> Referenced Values Array: Pointer
)
=> NVP Value: Text
```

| Parameter       | Type        | Description            |
|-----------------|-------------|------------------------|
| <i>NVP Name</i> | <b>Text</b> | Named value to extract |



|                                |                |                                       |
|--------------------------------|----------------|---------------------------------------|
| <i>Referenced Names Array</i>  | <b>Pointer</b> | <b>Pointer to names array</b>         |
| <i>Referenced Values Array</i> | <b>Pointer</b> | <b>Pointer to values array</b>        |
| <i>NVP Value</i>               | <b>Text</b>    | <b>Value matching <i>NVP Name</i></b> |

The method ***NVP\_Extract\_Values\_by\_Names\_s*** returns the value associated with a particular name from an NVP stack. The value returned will be the first occurrence of the specified name which is found in the names array of the NVP stack.

*NVP Name* is the name to find in the names array in the NVP stack, *Referenced Names Array*.

*Referenced Names Array* is a pointer to the names array for the NVP stack to be searching.

*Referenced Values Array* is a pointer to the values array for the NVP stack to be searching.

*NVP Value* is the value found matching *NVP Name* within the referenced NVP stack. If no match is found in the NVP stack for *NVP Name*, *NVP Value* will be set to empty.

**Note:** the method ***NVP\_Extract\_Values\_by\_Names\_s*** was added in BASH v1.5.1.



## **NVP\_Extract\_Values\_by\_Name\_x**

***NVP\_Extract\_Values\_by\_Name\_x***( *Packed NVP Text*; *NVP Name*; *Column Delimiter ASCII Value*; *Row Delimiter ASCII Value*) => *NVP Value*

***NVP\_Extract\_Values\_by\_Name\_x***  
 (  
     -> *Packed NVP Text*: **Text**  
     -> *NVP Name*: **Text**  
     -> *Column Delimiter ASCII Value*: **Longint**  
     -> *Row Delimiter ASCII Value*: **Longint**  
 )  
 => *NVP Value*: **Text**

| <b>Parameter</b>                    | <b>Type</b> | <b>Description</b>   |
|-------------------------------------|-------------|--|
| <i>Packed NVP Text</i>              | Text        | NVP stack packed in text   |
| <i>NVP Name</i>                     | Text        | Named value to extract   |
| <i>Column Delimiter ASCII Value</i> | Longint     | ASCII Value of the column delimiter used to pack the NVP stack into text |
| <i>Row Delimiter ASCII Value</i>    | Longint     | ASCII Value of the row delimiter used to pack the NVP stack into text    |
| <i>NVP Value</i>                    | Text        | Value matching <i>NVP Name</i>   |

The method ***NVP\_Extract\_Values\_by\_Names\_x*** returns the values associated with a particular name from a packed NVP stack. The value returned will be the first occurrence of the specified name which is found in the packed NVP stack.

*Packed NVP Text* is the NVP stack packed into a text variable (see the method ***NVP\_Pack\_to\_Text*** for packing and NVP stack into a text variable).

*NVP Name* is the name to find in the names array in the NVP stack, *Referenced Names Array*.

*Column Delimiter ASCII Value* is the ASCII value of the column delimiter used to pack the NVP stack.

*Row Delimiter ASCII Value* is the ASCII value of the row delimiter used to pack the NVP stack.

*NVP Value* is the value found matching *NVP Name* within the referenced NVP stack. If no match is found in the NVP stack for *NVP Name*, *NVP Value* will be set to empty.

**Note:** the method ***NVP\_Extract\_Values\_by\_Names\_x*** was added in BASH v1.5.1.



## **NVP\_Pack\_to\_Text**

***NVP\_Pack\_to\_Text***( *Referenced Names Array*; *Referenced Values Array*;  
*Column Delimiter ASCII Value*; *Row Delimiter ASCII Value*;  
*Trailing Row Delimiter Flag*) => *Packed NVP Text*

***NVP\_Pack\_to\_Text***

```
(
    -> Referenced Names Array: Pointer
    -> Referenced Values Array: Pointer
    -> Column Delimiter ASCII Value: Longint
    -> Row Delimiter ASCII Value: Longint
    -> Trailing Row Delimiter Flag: Boolean
)
=> Packed NVP Text: Text
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>   |
|-------------------------------------|----------------|--|
| <i>Referenced Names Array</i>       | <b>Pointer</b> | Pointer to names array of NVP stack  |
| <i>Referenced Values Array</i>      | <b>Pointer</b> | Pointer to values array of NVP stack                                       |
| <i>Column Delimiter ASCII Value</i> | <b>Longint</b> | ASCII Value of the column delimiter to use to pack the NVP stack into text |
| <i>Row Delimiter ASCII Value</i>    | <b>Longint</b> | ASCII Value of the row delimiter to use to pack the NVP stack into text    |
| <i>Trailing Row Delimiter Flag</i>  | <b>Boolean</b> | Flag to include the trailing row delimiter value in the packed NVP stack   |
| <i>Packed NVP Text</i>              | <b>Text</b>    | NVP stack packed into text with the options specified                      |

The method ***NVP\_Pack\_to\_Text*** packs a well formed NVP stack into a text variable using the options specified. The NVP stack must have at least one (1) pairing of names and values and it must be a well formed NVP stack.

*Referenced Names Array* is a pointer to the names array for the NVP stack to be packed.

*Referenced Values Array* is a pointer to the values array for the NVP stack to be packed.

*Column Delimiter ASCII Value* is the ASCII value of the column delimiter to use to pack the NVP stack.

*Row Delimiter ASCII Value* is the ASCII value of the row delimiter to use to pack the NVP stack.

*Trailing Row Delimiter Flag* is a boolean value to indicate whether the a row delimiter is to be placed after the last pairing within the packed NVP stack.

*Packed NVP Text* is the NVP stack packed into a text variable using all of options specified in calling this method.

**Note:** the method *NVP\_Pack\_to\_Text* was added in BASH v1.5.1.



## **NVP\_Parse\_to\_Arrays**

**NVP\_Parse\_to\_Arrays**( *Packed NVP Text*; *Referenced Names Array*;  
*Referenced Values Array*; *Column Delimiter ASCII Value*; *Row Delimiter ASCII Value*; *Comment ASCII Value*) => *NVP Count*

### **NVP\_Parse\_to\_Arrays**

```
(  
    -> Packed NVP Text: Text  
    -> Referenced Names Array: Pointer  
    -> Referenced Values Array: Pointer  
    -> Column Delimiter ASCII Value: Longint  
    -> Row Delimiter ASCII Value: Longint  
    -> Comment ASCII Value: Longint  
)  
=> NVP Count: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>   |
|-------------------------------------|----------------|--|
| <i>Packed NVP Text</i>              | <b>Text</b>    | NVP stack packed into text   |
| <i>Referenced Names Array</i>       | <b>Pointer</b> | Pointer to array to use as names array for unpacked NVP pairings         |
| <i>Referenced Values Array</i>      | <b>Pointer</b> | Pointer to array to use as values array for unpacked NVP pairings        |
| <i>Column Delimiter ASCII Value</i> | <b>Longint</b> | ASCII Value of the column delimiter used to pack the NVP stack into text |
| <i>Row Delimiter ASCII Value</i>    | <b>Longint</b> | ASCII Value of the row delimiter used to pack the NVP stack into text    |

|                            |         |   |
|----------------------------|---------|---|
| <i>Comment ASCII Value</i> | Longint | ASCII Value of the comment character used in the packed NVP stack   |
| <i>NVP Count</i>           | Longint | Number of pairings successfully extracted from the packed NVP stack |

The method ***NVP\_Parse\_to\_Arrays*** unpacks an NVP stack from a text variable using the options specified. The packed NVP stack must be well formed and formatted for the parsing routine to be successful.

*Packed NVP Text* is the NVP stack packed into a text variable which is to be parsed.

*Referenced Names Array* is a pointer to the array to hold the names of the pairings unpacked from *Packed NVP Text*..

*Referenced Values Array* is a pointer to the array to hold the values of the pairings unpacked from *Packed NVP Text*..

*Column Delimiter ASCII Value* is the ASCII value of the column delimiter used to pack the NVP stack.

*Row Delimiter ASCII Value* is the ASCII value of the row delimiter used to pack the NVP stack.

*Comment ASCII Value* is the ASCII value of the comment character to skip within the packed NVP stack. A comment byte used at the beginning of a row in a packed NVP stack will force the row to be skipped when parsed.

*NVP Count* is the number of pairings which this method parses from *Packed NVP Text* using the options specified.

**Note:** the method ***NVP\_Parse\_to\_Arrays*** was added in BASH v1.5.1.

# PTEXT Module

The PTEXT module provides simple parameter text replacement routines for use within 4th Dimension. With the use of parameter text values it is a simple matter to create general replacement and formatted routines for common values used in 4D based applications.

**Note:** the PTEXT module was added in BASH v1.5.7.

## Parameter Text Values

Parameter text (PText) values are simple text or binary values which have particular series of byte values embedded within them for use as placeholders. These placeholders are meant to be replaced with parameters which using the text or binary values within an application.

Placeholders within a PText value have the following format:

`^nn`

where *nn* is a number formatted to two digits. The following string is a valid, raw PText value containing two different placeholders:

The ^01 jumped over the ^02.

The following is a second example of a valid, raw PText value, again containing two different placeholders:

`<A HREF="mailto:^01">^02, ^01</A>`

If the second, raw PText value, above, were set into the variable `$xRawPText`, then the following function call:

`PTEXT_Set_Values_x($xRawPText;"foo@goo.com";"me")`

would return the value:

<A HREF="mailto:foo@goo.com">me, foo@goo.com</A>

Since placeholders contain numbers, the maximum number of unique placeholders allowed within a raw PText value is 99 (from ^01 to ^99).



## **PTEXT\_Set\_Values\_ax**

**PTEXT\_Set\_Values\_ax** ( *Raw PText* ; *Referenced Values* ) => *Populated PText*

**PTEXT\_Set\_Values\_ax**  
(  
    -> *Raw PText* : **Text**  
    -> *Referenced Values* : **Pointer**  
)  
=> *Populated PText* : **Text**

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>  |
|--------------------------|----------------|---|
| <i>Raw PText</i>         | <b>Text</b>    | Text value containing raw PText   |
| <i>Referenced Values</i> | <b>Pointer</b> | Referenced text array containing values to substitute into <i>Raw PText</i>                   |
| <i>Populated PText</i>   | <b>Text</b>    | Text value with substitutions listed in <i>Referenced Values</i> placed into <i>Raw PText</i> |

The method **PTEXT\_Set\_Values\_ax** will populate a specified raw PText with the indexed entries in a referenced text array and return the resulting text value.

*Raw PText* is the raw PText value in textual format which contains placeholders to be replaced.

*Referenced Values* is a pointer to a text array containing indexed entries to use as substitutes into *Raw PText* value.

*Populated PText* is the resulting *Raw PText* value with all of the substitutions values from *Referenced Values* placed.

Note: the method *PTEXT\_Set\_Values\_ax* was added in BASH v1.5.7.



## **PTEXT\_Set\_Values\_az**

**PTEXT\_Set\_Values\_az** ( *Referenced PText* ; *Referenced Values* )

**PTEXT\_Set\_Values\_az**

(  
    -> *Referenced PText* : **Pointer**  
    -> *Referenced Values* : **Pointer**  
)

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>  |
|--------------------------|----------------|---|
| <i>Referenced PText</i>  | <b>Pointer</b> | Pointer to BLOB containing PText value to perform substitution upon         |
| <i>Referenced Values</i> | <b>Pointer</b> | Referenced text array containing values to substitute into <i>Raw PText</i> |

The method *PTEXT\_Set\_Values\_az* will populate a referenced PText value within a BLOB with the indexed entries in a referenced text array.

*Referenced PText* is a pointer to a BLOB containing the PText value which is to have substitutions performed upon.

*Referenced Values* is a pointer to a text array containing indexed entries to use as substitutes into *Referenced PText* value.

Note: the method *PTEXT\_Set\_Values\_az* was added in BASH v1.5.7.



## **PTEXT\_Set\_Values\_x**

**PTEXT\_Set\_Values\_x** ( *Raw PText* ; *First Value* { ; *Second Value* { ; ... } } )  
=> *Populated PText*

**PTEXT\_Set\_Values\_x**

(



```

-> Raw PText : Text
-> First Value : Text
{
-> Second Value : Text
{
...
}
}
)

=> Populated PText : Text

```

| Parameter              | Type | Description   |
|------------------------|------|---|
| <i>Raw PText</i>       | Text | Text value containing raw PText   |
| <i>First Value</i>     | Text | Value to use as replacement into<br><i>Raw PText</i>  |
| <i>Populated PText</i> | Text | Text value with substitutions listed<br>in <i>Referenced Values</i> placed into<br><i>Raw PText</i> |

The method *PTEXT\_Set\_Values\_x* will populate a specified raw PText with one or more specified replacement values.

*Raw PText* is the raw PText value in textual format which contains placeholders to be replaced.

*First Value* is a text value to use as a replacement value into *Raw PText* value. One or more values may be passed to this method, as needed by the particular PText value.

*Populated PText* is the resulting *Raw PText* value with all of the substitutions values placed.

**Note:** the method *PTEXT\_Set\_Values\_x* was added in BASH v1.5.7.



## **PTEXT\_Set\_Values\_z**

**PTEXT\_Set\_Values\_z** (*Referenced PText* ; *First Value* { ; *Second Value* { ; ...  
}} ) => *Populated PText*

**PTEXT\_Set\_Values\_z**

```

(
-> Referenced PText : Pointer
-> First Value : Text

```

```

{      -> Second Value : Text
{
...
}
}
)

```

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>  |
|-------------------------|----------------|---|
| <i>Referenced PText</i> | <b>Pointer</b> | Pointer to BLOB containing PText value to perform substitution upon                           |
| <i>First Value</i>      | <b>Text</b>    | Value to use as replacement into <i>Raw PText</i>   |
| <i>Populated PText</i>  | <b>Text</b>    | Text value with substitutions listed in <i>Referenced Values</i> placed into <i>Raw PText</i> |

The method ***PTEXT\_Set\_Values\_z*** will populate a referenced PText value within a BLOB with one or more specified replacement values.

*Referenced PText* is a pointer to a BLOB containing the PText value which is to have substitutions performed upon.

*First Value* is a text value to use as a replacement value into *Referenced PText* value. One or more values may be passed to this method, as needed by the particular PText value.

**Note:** the method ***PTEXT\_Set\_Values\_z*** was added in BASH v1.5.7.

# PROS Module

The PROS module provides very basic functionality involving 4th Dimension processes. A few holes in the native functionality have been filled in and some functionality natively available has been more conveniently packaged by the methods in the PROS module.

In future versions of the BASH component, the basic contents of the PROS module will be expanded considerably to provide much greater, and more convenient, handling of 4th Dimension processes. As well, future components will rely heavily on the process handling capabilities that exist, and are to come, in the PROS module.

**Note:** the PROS module was added in BASH v1.5.4.



## PROS\_Delay\_Current

**PROS\_Delay\_Current** ( *Delay Tick Count* )

**PROS\_Delay\_Current**

(  
    -> *Delay Tick Count* : Longint  
)

| Parameter               | Type    | Description                    |
|-------------------------|---------|--------------------------------|
| <i>Delay Tick Count</i> | Longint | Ticks to delay current process |

The method **PROS\_Delay\_Current** will delay the current process for the specified number of ticks.

4D kernel processes, which can not be directly delayed, are held synchronously within this routine until the timeout has been reached. During this time, the process state will not read as delayed.

*Delay Tick Count* is the number of ticks to delay the current process.

Note: the method *PROS\_Delay\_Current* was added in BASH v1.5.4.

---

## **PROS\_Get\_Type**

**PROS\_Get\_Type** ( *Process ID* ) => *Process Type*

**PROS\_Get\_Type**  
(  
    -> *Process ID* : Longint  
)  
    => *Process Type* : Longint

| Parameter           | Type    | Description                          |
|---------------------|---------|--------------------------------------|
| <i>Process ID</i>   | Longint | 4D process ID to get the the type of |
| <i>Process Type</i> | Longint | Process type of <i>Process ID</i>    |

The method *PROS\_Get\_Type* will return the process type of the specified 4D process ID. Process types are also known as the process origin.

*Process ID* is the 4D process ID for the process to get the type of. *Process ID* must always be with respect to the current, local machine; this is not the actual process ID of remote processes on other machines.

*Process Type* is the process type code of the specified process *Process ID*. Valid values for *Process Type* are as follows:

| <u>Value</u> | <u>Meaning</u>               |
|--------------|------------------------------|
| -11          | Contextual Web Process       |
| -10          | Other 4D Process             |
| -9           | External Task                |
| -8           | Event Manager                |
| -7           | Apple Event Manager          |
| -6           | Serial Port Manager          |
| -5           | Indexing Process             |
| -4           | Cache Manager                |
| -3           | NonContextual Web Process    |
| -2           | Design Process               |
| -1           | User or Custom Menus Process |
| 0            | None                         |
| 1            | Creating from Programming    |

- |   |                            |
|---|----------------------------|
| 2 | Creating from Menu Command |
| 3 | Created from User Mode     |
| 4 | Other User Process         |

**Note:** the method *PROS\_Get\_Type* was added in BASH v1.5.4.



## **PROS\_Get\_UniqueID**

***PROS\_Get\_UniqueID*** ( *Process ID* ) => *Process Unique ID*

***PROS\_Get\_UniqueID***

```
(
    -> Process ID : Longint
)
=> Process Unique ID : Longint
```

| Parameter                | Type    | Description                            |
|--------------------------|---------|--|
| <i>Process ID</i>        | Longint | 4D process ID to get the unique ID of  |
| <i>Process Unique ID</i> | Longint | Unique process ID of <i>Process ID</i> |

The method *PROS\_Get\_UniqueID* will return the 4D unique process ID for a specified 4D process ID.

*Process ID* is the 4D process ID for the process to get the type of. *Process ID* must always be with respect to the current, local machine; this is not the actual process ID of remote processes on other machines.

*Process Unique ID* is the 4D unique process ID of the specified 4D process *Process ID*.

**Note:** due to a bug in 4D v6.7.0, this command does not return the correct value when used with this version of 4D.

**Note:** the method *PROS\_Get\_UniqueID* was added in BASH v1.5.4.

## RES Module

The RES module contains numerous resource management methods for use within 4th Dimension. This includes methods to manage opening and closing resource forks and accessing specific resource types. Methods are also available for setting and getting different resource properties and attributes. With future versions of the BASH component, the RES module will expand significantly.

### **'fMAP' Resource**

Documentation for the 'fMap' resource will be provided in a future release of the BASH component.

### **'HTbl' Resource**

Documentation for the 'HTbl' resource will be provided in a future release of the BASH component.

### **'LoCK' Resource**

Documentation for the 'LoCK' resource will be provided in a future release of the BASH component.

### **'MENV' Resource**

Documentation for the 'MENV' resource will be provided in a future release of the BASH component.

### **'WAGr' Resource**

Documentation for the 'fMap' resource will be provided in a future release of the BASH component.

## 'WPGGr' Resource

Documentation for the 'fMap' resource will be provided in a future release of the BASH component.

**Note:** the RES module was initially added in BASH v1.5.1.



### RES\_Close

**RES\_Close**( *Resource Fork File Reference* )

**RES\_Close**

(  
    *-> Resource Fork File Reference: Time*  
)

| Parameter                           | Type | Description                           |
|-------------------------------------|------|---------------------------------------|
| <i>Resource Fork File Reference</i> | Time | Resource fork file reference to close |

The method **RES\_Close** will close a resource fork which was previously opened within 4th Dimension. This method functions exactly the same as calling the native 4D command **CLOSE RESOURCE FORK**.

*Resource Fork File Reference* is the reference value to the resource fork previously opened to close within this method.

**Note:** the method **RES\_Close** was added in BASH v1.5.1.



### RES\_Create\_File

**RES\_Create\_File**( *Full Path*; *File Type*) => *Resource Fork File Reference*

**RES\_Create\_File**

```
(  
    -> Full Path: Text  
    -> File Type: Longint  
)  
=> Resource Fork File Reference: Time
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                                     |
|-------------------------------------|----------------|--|
| <i>Full Path</i>                    | <b>Text</b>    | Full path to new resource document to create           |
| <i>File Type</i>                    | <b>Longint</b> | File type of new resource document                     |
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference for new resource document |

The method **RES\_Create\_File** will create a new resource document, open it within 4th Dimension, and return the resource fork file reference for it. This method functions exactly the same as calling the native 4D command **Create resource file**.

*Full Path* is the full path to the resource document to create.

*File Type* is the file type of the new resource document being created. If *File Type* is zero (0), then the default file type will be assigned to the newly created resource document (i.e. 'res ' or ".res", as applicable by platform).

*Resource Fork File Reference* is the reference value to the resource fork of the newly created resource document.

**Note:** the method **RES\_Create\_File** was added in BASH v1.5.1.



## **RES\_Delete\_Resource**

**RES\_Delete\_Resource**( *Resource Fork File Reference*; *Resource Type*;  
*Resource ID*) => *Success Indicator*

**RES\_Delete\_Resource**



```
(
    -> Resource Fork File Reference: Time
    -> Resource Type: Longint
    -> Resource ID: Longint
)
=> Success Indicator: Longint
```

| Parameter                           | Type    | Description                                 |
|-------------------------------------|---------|---|
| <i>Resource Fork File Reference</i> | Time    | Resource fork file reference to delete from |
| <i>Resource Type</i>                | Longint | Resource type to delete                     |
| <i>Resource ID</i>                  | Longint | Resource ID to delete                       |
| <i>Success Indicator</i>            | Longint | qi for successfully deleting resource       |

The method ***RES\_Delete\_Resource*** will delete a particular resource. The resource must be identified by the resource file, resource type, and resource ID. This method is functionally equivalent to using the netive 4D command **DELETE RESOURCE**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to delete from.

*Resource Type* is the resource type to delete.

*Resource ID* is the resource ID to delete.

*Success Indicator* is an indicator value for whether the deletion was successful. If *Success Indicator* is zero (0) then the resource was not deleted; if *Success Indicator* is one (1) then the resource was successully deleted.

**Note:** the method ***RES\_Delete\_Resource*** was added in BASH v1.5.1.



## **RES\_ERROR**

***RES\_ERROR*** ( *BASH Error Number*; *Special Error Text*; *Calling Method Name* )

***RES\_ERROR***

```
(
    -> BASH Error Number: Longint
    -> Special Error Text: Text
    -> Calling Method Name: Text
)
```

| Parameter           | Type    | Description   |
|---------------------|---------|---|
| BASH Error Number   | Longint | Internal NULL error number                              |
| Special Error Text  | Text    | Special text to describe the exact error instance       |
| Calling Method Name | Text    | Name of the method that the error condition occurred in |

The method **RES\_ERROR** acts as a callback method from within the RES module for errors that may occur. Any time an error condition is detected within the RES module, a call to the method **RES\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the DSS method which call the **RES\_ERROR** method.

The **RES\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed

**Note:** the method **RES\_ERROR** was added in BASH v1.5.1.



## **RES\_Get\_Fork\_Size**

**RES\_Get\_Fork\_Size** ( Document Full Path ) => Resource Fork Bytes

**RES\_Get\_Fork\_Size**

```
(
    -> Document Full Path : Text
)
=> Resource Fork Bytes: Longint
```

| <b>Parameter</b>           | <b>Type</b>    | <b>Description</b>   |
|----------------------------|----------------|--|
| <i>Document Full Path</i>  | <b>Text</b>    | Full path to document                                      |
| <i>Resource Fork Bytes</i> | <b>Longint</b> | Number of bytes in the resource fork of specified document |

The method *RES\_Get\_Fork\_Size* returns the number of bytes in the resource fork of a specified document. On Windows, it retrieves the size of the resource document, if any, equivalent to the resource fork of a single document on Macintosh.

*Document Full Path* is the full path to the document to get the resource fork size of.

*Resource Fork Bytes* is the number of bytes in the resource fork of the document *Document Full Path* . If the document does not exist, *Resource Fork Bytes* will be set to negative one (-1). If the document specified in *Document Full Path* is a resource document and the current OS is Windows, *Resource Fork Bytes* will be set to negative two (-2).

**Note:** the method *RES\_Get\_Fork\_Size* was added in BASH v1.5.6.



## **RES\_Get\_Resource\_List**

**RES\_Get\_Resource\_List**( *Resource Fork File Reference*; *Resource Type*;  
*Referenced Resource IDs*; *Referenced Resource Names*)

**RES\_Get\_Resource\_List**

```
(
    -> Resource Fork File Reference: Time
    -> Resource Type: Longint
    -> Referenced Resource IDs: Pointer
    -> Referenced Resource Names: Pointer
)
```

| <b>Parameter</b>                    | <b>Type</b>            | <b>Description</b>  |
|-------------------------------------|------------------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>            | Resource fork file reference to work with                           |
| <i>Resource Type Referenced</i>     | <b>Longint Pointer</b> | Resource type to work with<br>Pointer to array to hold resource IDs |
| <i>Resource IDs Referenced</i>      | <b>Pointer</b>         | Pointer to array to hold resource names                             |
| <i>Resource Names</i>               |                        |   |

The method ***RES\_Get\_Resource\_List*** retrieves a list of all of the resources of a specified resource type from a specified resource document. This method is functionally equivalent to the native 4D command **RESOURCE LIST**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource Type* is the resource type to work with.

*Referenced Resource IDs* is a pointer to a longint array which will contain the resource IDs matching *Resource Type* in the resource document *Resource Fork File Reference*.

*Referenced Resource Names* is a pointer to a text array which will contain the resource names matching *Resource Type* in the resource document *Resource Fork File Reference*.

**Note:** the values within *Referenced Resource IDs* and *Referenced Resource Names* are a well formed stack.

**Note:** the method ***RES\_Get\_Resource\_List*** was added in BASH v1.5.1.



## **RES\_Get\_TEXT\_Resource**

***RES\_Get\_TEXT\_Resource***( *Resource Fork File Reference*; *Resource ID*) =>  
*Resource Text Value*

## ***RES\_Get\_TEXT\_Resource***

```
(  
    -> Resource Fork File Reference: Time  
    -> Resource ID: Longint  
)  
=> Resource Text Value: Text
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Resource Text Value</i>          | <b>Text</b>    | Text value stored in specified resource   |

The method *RES\_Get\_TEXT\_Resource* retrieves the contents of a 'TEXT' resource from a specified resource document. This method is functionally equivalent to the native 4D command **Get text resource**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Resource Text Value* is the contents of the specified 'TEXT' resource.

**Note:** the method *RES\_Get\_TEXT\_Resource* was added in BASH v1.5.1.



## ***RES\_Load\_cicn***

***RES\_Load\_cicn***( *Resource Fork File Reference*; *Resource ID*; *Referenced Picture*) => *Success Indicator*

```
RES_Load_cicn  
(  
    -> Resource Fork File Reference: Time  
    -> Resource ID: Longint  
    -> Referenced Picture: Pointer  
)  
=> Success Indicator: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                                |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with         |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                          |
| <i>Referenced Picture</i>           | <b>Pointer</b> | Pointer to picture variable to load resource into |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for loaded successfully                        |

The method ***RES\_Load\_cicn*** retrieves a the contents of an icon resource from a specified resource document. This method is functionally equivalent to the native 4D command **GET ICON RESOURCE**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced Picture* is a pointer to a picture variable to load the resource contents into.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method ***RES\_Load\_cicn*** was added in BASH v1.5.1.



## **RES\_Load\_fMap**

***RES\_Load\_fMAP***( *Resource Fork File Reference*; *Resource ID*; *Referenced Title*; *Referenced Macintosh Types*; *Referenced Windows Types*; *Referenced Macintosh Creators*; *Referenced MIME Types*; *Referenced Parm Bits*) => *Success Indicator*

### ***RES\_Load\_fMAP***

(

- > *Resource Fork File Reference*: **Time**
- > *Resource ID*: **Longint**
- > *Referenced Title*: **Pointer**
- > *Referenced Macintosh Types*: **Pointer**
- > *Referenced Windows Types*: **Pointer**

-> *Referenced Macintosh Creators*: **Pointer**  
-> *Referenced MIME Types*: **Pointer**  
-> *Referenced Parm Bits*: **Pointer**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                     | <b>Type</b>    | <b>Description</b>                        |
|--------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i>  | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                   | <b>Longint</b> | Resource ID to work with                  |
| <i>Referenced Title</i>              | <b>Pointer</b> | not available at this time                |
| <i>Referenced Macintosh Types</i>    | <b>Pointer</b> | not available at this time                |
| <i>Referenced Windows Types</i>      | <b>Pointer</b> | not available at this time                |
| <i>Referenced Macintosh Creators</i> | <b>Pointer</b> | not available at this time                |
| <i>Referenced MIME Types</i>         | <b>Pointer</b> | not available at this time                |
| <i>Referenced Parm Bits</i>          | <b>Pointer</b> | not available at this time                |
| <i>Success Indicator</i>             | <b>Longint</b> | qi for loaded successfully                |

The method *RES\_Load\_fMap* retrieves the contents of an 'fMap' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

The remainder of the documentation for this method, including the exact structure of the 'fMap' resource is being left for future versions of the BASH component.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method *RES\_Load\_fMap* was added in BASH v1.5.1.



## RES\_Load\_HTbl

**RES\_Load\_HTbl** ( *Resource File Reference* ; *Resource ID* ; *Referenced Resource* ) => *Success*

**RES\_Load\_HTbl**  
(  
    -> *Resource File Reference* : **Time**  
    -> *Resource ID* : **Longint**  
    -> *Referenced Resource* : **Pointer**  
)  
=> *Success*: **Longint**

| Parameter                      | Type           | Description                                  |
|--------------------------------|----------------|--|
| <i>Resource File Reference</i> | <b>Time</b>    | Resource fork file referenced to work with   |
| <i>Resource ID</i>             | <b>Longint</b> | Resource ID to work with                     |
| <i>Referenced Resource</i>     | <b>Pointer</b> | Referenced BLOB to load 'HTbl' resource into |
| <i>Success</i>                 | <b>Longint</b> | qi for loaded successfully                   |

The method **RES\_Load\_HTbl** retrieves the contents of a 'HTbl' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced Resource* is a pointer to a BLOB to contain the resource retrieved.

*Success* is an indicator value for whether the loading was successful. If *Success* is zero (0) then the resource was not loaded; if *Success* is one (1) then the resource was successfully loaded.

**Note:** the method **RES\_Load\_HTbl** was added in BASH v1.5.5.



## RES\_Load\_LoCK



**RES\_Load\_LoCK**( *Resource Fork File Reference*; *Resource ID*; *Referenced Lock Pin Names*; *Referenced Low Flags*; *Referenced High Flags*)  
=> *Success Indicator*

**RES\_Load\_LoCK**  
(  
-> *Resource Fork File Reference*: **Time**  
-> *Resource ID*: **Longint**  
-> *Referenced Lock Pin Names*: **Pointer**  
-> *Referenced Low Flags*: **Pointer**  
-> *Referenced High Flags*: **Pointer**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Referenced Lock Pin Names</i>    | <b>Pointer</b> | not available at this time                |
| <i>Referenced Low Flags</i>         | <b>Pointer</b> | not available at this time                |
| <i>Referenced High Flags</i>        | <b>Pointer</b> | not available at this time                |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for loaded successfully                |

The method **RES\_Load\_LoCK** retrieves the contents of a 'LoCK' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

The remainder of the documentation for this method, including the exact structure of the 'LoCK' resource is being left for future versions of the BASH component.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method *RES\_Load\_LoCK* was added in BASH v1.5.1.



## **RES\_Load\_MBAR**

**RES\_Load\_MBAR**( *Resource Fork File Reference*; *Resource ID*; *Referenced MENU Resource IDs*) => *Success Indicator*

### **RES\_Load\_MBAR**

(  
    -> *Resource Fork File Reference*: **Time**  
    -> *Resource ID*: **Longint**  
    -> *Referenced MENU Resource IDs*: **Pointer**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>  |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with                                     |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with  |
| <i>Referenced MENU Resource IDs</i> | <b>Pointer</b> | Pointer to array to hold 'MENU' resource IDs within specified 'MBAR' resource |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for loaded successfully  |

The method *RES\_Load\_MBAR* retrieves the contents of an 'MBAR' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced MENU Resource IDs* is a pointer to a longint array which will hold the 'MENU' resource IDs referenced in the specified 'MBAR' resource.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method *RES\_Load\_MBAR* was added in BASH v1.5.1.



## **RES\_Load\_MENU**

**RES\_Load\_MENU**( *Resource Fork File Reference*; *Resource ID*; *Referenced Menu Item Titles*; *Referenced Menu Item States*; *Referenced Menu Item Styles*; *Referenced Menu Item Keys*; *Referenced Menu Item Marks*) => *Success Indicator*

### **RES\_Load\_MENU**

```
(  
    -> Resource Fork File Reference: Time  
    -> Resource ID: Longint  
    -> Referenced Menu Item Titles: Pointer  
    -> Referenced Menu Item States: Pointer  
    -> Referenced Menu Item Styles: Pointer  
    -> Referenced Menu Item Keys: Pointer  
    -> Referenced Menu Item Marks: Pointer  
)  
=> Success Indicator: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Referenced Menu Item Titles</i>  | <b>Pointer</b> | Pointer to array to hold menu item titles |
| <i>Referenced Menu Item States</i>  | <b>Pointer</b> | Pointer to array to hold menu item states |
| <i>Referenced Menu Item Styles</i>  | <b>Pointer</b> | Pointer to array to hold menu item styles |
| <i>Referenced Menu Item Keys</i>    | <b>Pointer</b> | Pointer to array to hold menu items keys  |
| <i>Referenced Menu Item Marks</i>   | <b>Pointer</b> | Pointer to array to hold menu items marks |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for loaded successfully                |

The method *RES\_Load\_MENU* retrieves the contents of a 'MENU' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced Menu Item Titles* is a pointer to a text array which will hold the menu item names for the specified 'MENU' resource.

*Referenced Menu Item States* is a pointer to a longint array which will hold the menu item states for the specified 'MENU' resource.

*Referenced Menu Item Styles* is a pointer to a longint array which will hold the menu item styles for the specified 'MENU' resource.

*Referenced Menu Item Keys* is a pointer to a longint array which will hold the menu item keys for the specified 'MENU' resource.

*Referenced Menu Item Marks* is a pointer to a longint array which will hold the menu item marks for the specified 'MENU' resource.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the values within *Referenced Template Referenced Menu Item Titles*, *Referenced Menu Item States*, *Referenced Menu Item Styles*, *Referenced Menu Item Keys*, and *Referenced Menu Item Marks* are a well formed stack.

**Note:** the method *RES\_Load\_MENU* was added in BASH v1.5.1.



## **RES\_Load\_MENV**

**RES\_Load\_MENV**( *Resource Fork File Reference*; *Resource ID*; *Referenced Menu Item Names*; *Referenced Method Names*) => *Success Indicator*

## **RES\_Load\_MENV**

```
(  
    -> Resource Fork File Reference: Time  
    -> Resource ID: Longint  
    -> Referenced Menu Item Names: Pointer  
    -> Referenced Method Names: Pointer  
)  
=> Success Indicator: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Referenced Menu Item Names</i>   | <b>Pointer</b> | not available at this time                |
| <i>Referenced Method Names</i>      | <b>Pointer</b> | not available at this time                |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for loaded successfully                |

The method **RES\_Load\_MENV** retrieves the contents of a 'MENV' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

The remainder of the documentation for this method, including the exact structure of the 'MENV' resource is being left for future versions of the BASH component.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method **RES\_Load\_MENV** was added in BASH v1.5.1.



## **RES\_Load\_PICT**

**RES\_Load\_PICT**( *Resource Fork File Reference*; *Resource ID*; *Referenced Picture*) => *Success Indicator*

### **RES\_Load\_PICT**

(  
-> *Resource Fork File Reference*: **Time**  
-> *Resource ID*: **Longint**  
-> *Referenced Picture*: **Pointer**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                                |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with         |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                          |
| <i>Referenced Picture</i>           | <b>Pointer</b> | Pointer to picture variable to load resource into |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for loaded successfully                        |

The method **RES\_Load\_PICT** retrieves the contents of a 'PICT' resource from a specified resource document. This method is functionally equivalent to the native 4th Dimension command **GET PICTURE RESOURCE**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced Picture* is a pointer to a picture variable to load the resource contents into.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method **RES\_Load\_PICT** was added in BASH v1.5.1.



### **RES\_Load\_TMPL**

**RES\_Load\_TMPL**( *Resource Fork File Reference*; *Resource ID*; *Referenced Template Item Titles*; *Referenced Template Field Types*) => *Success Indicator*

**RES\_Load\_TMPL**

```
(
    -> Resource Fork File Reference: Time
    -> Resource ID: Longint
    -> Referenced Template Item Titles: Pointer
    -> Referenced Template Field Types: Pointer
)
=> Success Indicator: Longint
```

| <b>Parameter</b>                       | <b>Type</b>    | <b>Description</b>   |
|--|----------------|--|
| <i>Resource Fork File Reference</i>    | <b>Time</b>    | Resource fork file reference to work with                              |
| <i>Resource ID</i>                     | <b>Longint</b> | Resource ID to work with   |
| <i>Referenced Template Item Titles</i> | <b>Pointer</b> | Pointer to text array to hold template item titles which are loaded    |
| <i>Referenced Template Field Types</i> | <b>Pointer</b> | Pointer to longint array to hold template field types which are loaded |
| <i>Success Indicator</i>               | <b>Longint</b> | qi for loaded successfully   |

The method **RES\_Load\_TMPL** retrieves the contents of a 'PICT' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced Template Item Titles* is a pointer to a text array which will hold the template item titles which are loaded from the specified resource.

*Referenced Template Field Types* is a pointer to a longint array which will hold the template field types which are loaded from the specified resource.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0)

then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the values within *Referenced Template Item Titles* and *Referenced Template Item Titles* are a well formed stack.

**Note:** the method *RES\_Load\_TMPL* was added in BASH v1.5.1.



## **RES\_Load\_WAGr**

**RES\_Load\_WAGr**( *Resource Fork File Reference*; *Resource ID*; *Referenced Lock Code*; *Referenced Table Name*; *Referenced Action Titles*; *Referenced Action Values*; *Referenced Method Names*; *Referenced Link Titles*; *Referenced Resource IDs*; *Referenced Pin Indices*; *Referenced Page Flags*) => *Success Indicator*

### **RES\_Load\_WAGr**

```
(  
    -> Resource Fork File Reference: Time  
    -> Resource ID: Longint  
    -> Referenced Lock Code: Pointer  
    -> Referenced Table Name: Pointer  
    -> Referenced Action Titles: Pointer  
    -> Referenced Action Values: Pointer  
    -> Referenced Method Names: Pointer  
    -> Referenced Link Titles: Pointer  
    -> Referenced Resource IDs: Pointer  
    -> Referenced Pin Indices: Pointer  
    -> Referenced Page Flags: Pointer  
)  
=> Success Indicator: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Referenced Lock Code</i>         | <b>Pointer</b> | not available at this time                |
| <i>Referenced Table Name</i>        | <b>Pointer</b> | not available at this time                |



|                                 |                |                                   |
|---------------------------------|----------------|-----------------------------------|
| <i>Referenced Action Titles</i> | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Referenced Action Values</i> | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Referenced Method Names</i>  | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Referenced Link Titles</i>   | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Referenced Resource IDs</i>  | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Referenced Pin Indices</i>   | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Referenced Page Flags</i>    | <b>Pointer</b> | <b>not available at this time</b> |
| <i>Success Indicator</i>        | <b>Longint</b> | <b>qi for loaded successfully</b> |

The method *RES\_Load\_WAGr* retrieves the contents of a 'WAGr' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

The remainder of the documentation for this method, including the exact structure of the 'WAGr' resource is being left for future versions of the BASH component.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method *RES\_Load\_WAGr* was added in BASH v1.5.1.



## **RES\_Load\_WPGr**

**RES\_Load\_WPGr**( *Resource Fork File Reference*; *Resource ID*; *Referenced Global Lock Code*; *Referenced Global Pin Index*; *Referenced File Names*; *Referenced Resource IDs*; *Referenced Pin Indices*; *Referenced Link Titles*; *Referenced Method Names*; *Referenced*

Low Product Flags; Referenced High Product Flags) => Success Indicator

### ***RES\_Load\_WPGr***

```
(
    -> Resource Fork File Reference: Time
    -> Resource ID: Longint
    -> Referenced Global Lock Code: Pointer
    -> Referenced Global Pin Index: Pointer
    -> Referenced File Names: Pointer
    -> Referenced Resource IDs: Pointer
    -> Referenced Pin Indices: Pointer
    -> Referenced Link Titles: Pointer
    -> Referenced Method Names: Pointer
    -> Referenced Low Product Flags: Pointer
    -> Referenced High Product Flags: Pointer
)
=> Success Indicator: Longint
```

| <b>Parameter</b>              | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------|----------------|---|
| Resource Fork File Reference  | <b>Time</b>    | Resource fork file reference to work with |
| Resource ID                   | <b>Longint</b> | Resource ID to work with                  |
| Referenced Global Lock Code   | <b>Pointer</b> | not available at this time                |
| Referenced Global Pin Index   | <b>Pointer</b> | not available at this time                |
| Referenced File Names         | <b>Pointer</b> | not available at this time                |
| Referenced Resource IDs       | <b>Pointer</b> | not available at this time                |
| Referenced Pin Indices        | <b>Pointer</b> | not available at this time                |
| Referenced Link Titles        | <b>Pointer</b> | not available at this time                |
| Referenced Method Names       | <b>Pointer</b> | not available at this time                |
| Referenced Low Product Flags  | <b>Pointer</b> | not available at this time                |
| Referenced High Product Flags | <b>Pointer</b> | not available at this time                |
| Success Indicator             | <b>Longint</b> | qi for loaded successfully                |

The method *RES\_Load\_WPGr* retrieves the contents of a 'WPGr' resource from a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

The remainder of the documentation for this method, including the exact structure of the 'WPGGr' resource is being left for future versions of the BASH component.

*Success Indicator* is an indicator value for whether the loading was successful. If *Success Indicator* is zero (0) then the resource was not loaded; if *Success Indicator* is one (1) then the resource was successfully loaded.

**Note:** the method *RES\_Load\_WPGGr* was added in BASH v1.5.1.



## **RES\_Make\_TMPL\_f\_Arrays**

**RES\_Make\_TMPL\_f\_Arrays** (*Referenced BLOB; Referenced Template Item Titles; Referenced Template Field Types*) => *Success Indicator*

### **RES\_Make\_TMPL\_f\_Arrays**

```
(  
    -> Referenced BLOB: Pointer  
    -> Referenced Template Item Titles: Pointer  
    -> Referenced Template Field Types: Pointer  
)  
=> Success Indicator: Longint
```

| <b>Parameter</b>                       | <b>Type</b>    | <b>Description</b>                                       |
|--|----------------|--|
| <i>Referenced BLOB</i>                 | <b>Pointer</b> | Pointer to BLOB to contain 'TMPL' resource created       |
| <i>Referenced Template Item Titles</i> | <b>Pointer</b> | Pointer to text array containing template item titles    |
| <i>Referenced Template Field Types</i> | <b>Pointer</b> | Pointer to longint array containing template field types |
| <i>Success Indicator</i>               | <b>Longint</b> | qi for created successfully                              |

The method *RES\_Make\_TMPL\_f\_Arrays* will create a 'TMPL' resource from the values specified. The 'TMPL'

resource will be placed into a referenced BLOB value for further use and manipulation.

*Referenced BLOB* is a pointer to a BLOB to place the 'TMPL' resource created into.

*Referenced Template Item Titles* is a pointer to a text array containing the template item titles to be created in the 'TMPL' resource.

*Referenced Template Field Types* is a pointer to a longint array containing the template field types to be created in the 'TMPL' resource.

*Success Indicator* is an indicator value for whether the creation was successful. If *Success Indicator* is zero (0) then the resource was not created; if *Success Indicator* is one (1) then the resource was successfully created.

**Note:** the method *RES\_Make\_TMPL\_f\_Arrays* was added in BASH v1.5.1.



## RES\_Open

**RES\_Open**( *Full Path* ) => *Resource Fork File Reference*

**RES\_Open**

```
(  
    -> Full Path: Text  
)  
=> Resource Fork File Reference: Time
```

| Parameter                           | Type        | Description                            |
|-------------------------------------|-------------|--|
| <i>Full Path</i>                    | <b>Text</b> | Full path to resource document to open |
| <i>Resource Fork File Reference</i> | <b>Time</b> | Resource fork file reference opened    |

The method **RES\_Open** will open a resource fork within 4th Dimension and return a resource fork file reference for accessing the contents. This method functions

exactly the same as calling the native 4D command **Open resource fork**.

*Full Path* is the full path to the resource document to open within this method.

*Resource Fork File Reference* is the reference value to the resource fork opened within this method. If *Resource Fork File Reference* is NULL then the resource document specified failed to be opened.

**Note:** there is no harm or error condition which occurs if a resource document that is already opened within 4D is opened again. The same resource fork file reference will again be returned for use and there is no need to subsequently close the resource document multiple times.

**Note:** the method *RES\_Open* was added in BASH v1.5.1.



## **RES\_Open\_4DApplication**

**RES\_Open\_4DApplication**=> *Resource Fork File Reference*

**RES\_Open\_4DApplication**

=> *Resource Fork File Reference: Time*

| <b>Parameter</b>                    | <b>Type</b> | <b>Description</b>                         |
|-------------------------------------|-------------|--|
| <i>Resource Fork File Reference</i> | <b>Time</b> | <b>Resource fork file reference opened</b> |

The method **RES\_Open\_4DApplication** will open the resource fork of the current 4D application and return a resource fork file reference for accessing the contents.

*Resource Fork File Reference* is the reference value to the resource fork opened within this method. If *Resource Fork File Reference* is NULL then the resource fork failed to be opened.

**Note:** there is no harm or error condition which occurs if this method is called multiple times within the same

4D session. The same resource fork file reference will be returned for each subsequent call to this method. Under no circumstances though should you ever close the resource fork of the current 4D application.

**Note:** the method *RES\_Open\_4DApplication* was added in BASH v1.5.1.



## **RES\_Open\_BASH**

**RES\_Open\_BASH** => *Resource Fork File Reference*

**RES\_Open\_BASH**

=> *Resource Fork File Reference: Time*

| <b>Parameter</b>                    | <b>Type</b> | <b>Description</b>                         |
|-------------------------------------|-------------|--|
| <i>Resource Fork File Reference</i> | <b>Time</b> | <b>Resource fork file reference opened</b> |

The method *RES\_Open\_BASH* will open the resource fork of the current BASH Affix document (it should be in one of the 4DX directories) and return a resource fork file reference for accessing the contents.

*Resource Fork File Reference* is the reference value to the resource fork opened within this method. If *Resource Fork File Reference* is NULL then the resource fork failed to be opened.

**Note:** there is no harm or error condition which occurs if this method is called multiple times within the same 4D session. The same resource fork file reference will be returned for each subsequent call to this method.

**Note:** the method *RES\_Open\_BASH* was added in BASH v1.5.3.



## **RES\_Open\_DataFile**

**RES\_Open\_DataFile** => *Resource Fork File Reference*

## **RES\_Open\_DataFile**

=> *Resource Fork File Reference: Time*

| Parameter                           | Type | Description                         |
|-------------------------------------|------|-------------------------------------|
| <i>Resource Fork File Reference</i> | Time | Resource fork file reference opened |

The method **RES\_Open\_DataFile** will open the resource fork of the current 4D data file and return a resource fork file reference for accessing the contents.

*Resource Fork File Reference* is the reference value to the resource fork opened within this method. If *Resource Fork File Reference* is NULL then the resource fork failed to be opened.

**Note:** there is no harm or error condition which occurs if this method is called multiple times within the same 4D session. The same resource fork file reference will be returned for each subsequent call to this method.

**Note:** the method **RES\_Open\_DataFile** was added in BASH v1.5.1.



## **RES\_Open\_Structure**

**RES\_Open\_Structure**=> *Resource Fork File Reference*

### **RES\_Open\_Structure**

=> *Resource Fork File Reference: Time*

| Parameter                           | Type | Description                         |
|-------------------------------------|------|-------------------------------------|
| <i>Resource Fork File Reference</i> | Time | Resource fork file reference opened |

The method **RES\_Open\_Structure** will open the resource fork of the current 4D structure file and return a resource fork file reference for accessing the contents.

*Resource Fork File Reference* is the reference value to the resource fork opened within this method. If *Resource*

*Fork File Reference* is NULL then the resource fork failed to be opened.

**Note:** there is no harm or error condition which occurs if this method is called multiple times within the same 4D session. The same resource fork file reference will be returned for each subsequent call to this method. Under no circumstances though should you ever close the resource fork of the current 4D structure file.

**Note:** the method *RES\_Open\_Structure* was added in BASH v1.5.1.



## **RES\_Parse\_HTbl\_Cells**

**RES\_Parse\_HTbl\_Cells** ( *Referenced Resource ; Beginning Offset ; Referenced Cell IDs ; Referenced Cell Column Starts ; Referenced Cell Column Ends ; Referenced Cell Nth Columns ; Referenced Cell Nth Column Offsets ; Referenced Cell Horizontal Alignments ; Referenced Cell Vertical Alignments ; Referenced Cell Column Spans ; Referenced Cell Row Spans ; Referenced Cell Widths ; Referenced Cell Heights ; Referenced Cell Background Colors ; Referenced Cell Height Percentage Indicators ; Referenced Cell NoWrap Indicators* ) => *Offset*

### **RES\_Parse\_HTbl\_Cells**

(

- > *Referenced Resource* : **Pointer**
- > *Beginning Offset* : **Longint**
- > *Referenced Cell IDs* : **Pointer**
- > *Referenced Cell Column Starts* : **Pointer**
- > *Referenced Cell Column Ends* : **Pointer**
- > *Referenced Cell Nth Columns* : **Pointer**
- > *Referenced Cell Nth Column Offsets* : **Pointer**
- > *Referenced Cell Horizontal Alignments* : **Pointer**
- > *Referenced Cell Vertical Alignments* : **Pointer**
- > *Referenced Cell Column Spans* : **Pointer**
- > *Referenced Cell Row Spans* : **Pointer**
- > *Referenced Cell Widths* : **Pointer**
- > *Referenced Cell Heights* : **Pointer**
- > *Referenced Cell Background Colors* : **Pointer**
- > *Referenced Cell Height Percentage Indicators* : **Pointer**
- > *Referenced Cell NoWrap Indicators* : **Pointer**



)

=> Offset : Longint

| <b>Parameter</b>                                    | <b>Type</b> | <b>Description</b>                          |
|---|-------------|---|
| <i>Referenced Resource</i>                          | Pointer     | Referenced BLOB containing 'HTbl' resource  |
| <i>Beginning Offset</i>                             | Longint     | not available at this time                  |
| <i>Referenced Cell IDs</i>                          | Pointer     | not available at this time                  |
| <i>Referenced Cell Column Starts</i>                | Pointer     | not available at this time                  |
| <i>Referenced Cell Column Ends</i>                  | Pointer     | not available at this time                  |
| <i>Referenced Cell Nth Columns</i>                  | Pointer     | not available at this time                  |
| <i>Referenced Cell Nth Column Offsets</i>           | Pointer     | not available at this time                  |
| <i>Referenced Cell Horizontal Alignments</i>        | Pointer     | not available at this time                  |
| <i>Referenced Cell Vertical Alignments</i>          | Pointer     | not available at this time                  |
| <i>Referenced Cell Column Spans</i>                 | Pointer     | not available at this time                  |
| <i>Referenced Cell Row Spans</i>                    | Pointer     | not available at this time                  |
| <i>Referenced Cell Widths</i>                       | Pointer     | not available at this time                  |
| <i>Referenced Cell Heights</i>                      | Pointer     | not available at this time                  |
| <i>Referenced Cell Background Colors</i>            | Pointer     | not available at this time                  |
| <i>Referenced Cell Height Percentage Indicators</i> | Pointer     | not available at this time                  |
| <i>Referenced Cell NoWrap Indicators</i>            | Pointer     | not available at this time                  |
| <i>Offset</i>                                       | Longint     | Ending offset after parsing 'HTbl' resource |

The method *RES\_Parse\_HTbl\_Cells* will parse HTML table cell descriptors from a referenced 'HTbl' resource.

All parameters for this method are not documented at this time. Future versions of the BASH component will fully describe the use of this method.

**Note:** the method *RES\_Parse\_HTbl\_Cells* was added in BASH v1.5.5.



## RES\_Parse\_HTbl\_Rows

**RES\_Parse\_HTbl\_Rows** ( *Referenced Resource ; Beginning Offset ; Referenced Row Starts ; Referenced Row Ends ; Referenced Row Nths ; Referenced Row Nths Offsets ; Referenced Row Horizontal Alignments ; Referenced Row Vertical Alignments ; Referenced Row Background Colors ; Referenced Row Heights ; Referenced Row Heights Percentage Indicators ; Referenced Row Packed Column IDs* ) => *Offset*

### RES\_Parse\_HTbl\_Rows

```
(
    -> Referenced Resource : Pointer
    -> Beginning Offset : Longint
    -> Referenced Row Starts : Pointer
    -> Referenced Row Ends : Pointer
    -> Referenced Row Nths : Pointer
    -> Referenced Row Nths Offsets : Pointer
    -> Referenced Row Horizontal Alignments : Pointer
    -> Referenced Row Vertical Alignments : Pointer
    -> Referenced Row Background Colors : Pointer
    -> Referenced Row Heights : Pointer
    -> Referenced Row Heights Percentage Indicators : Pointer
    -> Referenced Row Packed Column IDs : Pointer
)
=> Offset : Longint
```

| Parameter                    | Type           | Description                                |
|------------------------------|----------------|--|
| <i>Referenced Resource</i>   | <b>Pointer</b> | Referenced BLOB containing 'HTBl' resource |
| <i>Beginning Offset</i>      | <b>Longint</b> | not available at this time                 |
| <i>Referenced Row Starts</i> | <b>Pointer</b> | not available at this time                 |
| <i>Referenced Row Ends</i>   | <b>Pointer</b> | not available at this time                 |

|  |         |   |
|--|---------|---|
| Referenced Row Nths                          | Pointer | not available at this time                  |
| Referenced Row Nths Offsets                  | Pointer | not available at this time                  |
| Referenced Row Horizontal Alignments         | Pointer | not available at this time                  |
| Referenced Row Vertical Alignments           | Pointer | not available at this time                  |
| Referenced Row Background Colors             | Pointer | not available at this time                  |
| Referenced Row Heights                       | Pointer | not available at this time                  |
| Referenced Row Heights Percentage Indicators | Pointer | not available at this time                  |
| Referenced Row Packed Column IDs             | Pointer | not available at this time                  |
| Offset                                       | Longint | Ending offset after parsing 'HTbl' resource |

The method *RES\_Parse\_HTbl\_Rows* will parse HTML table row descriptors from a referenced 'HTbl' resource.

All parameters for this method are not documented at this time. Future versions of the BASH component will fully describe the use of this method.

**Note:** the method *RES\_Parse\_HTbl\_Rows* was added in BASH v1.5.5.



## RES\_Parse\_HTbl\_Table

**RES\_Parse\_HTbl\_Table** ( Referenced Resource ; Referenced Table Border ; Referenced Table Width ; Referenced Table Height ; Referenced Table Cell Padding ; Referenced Table Cell Spacing ; Referenced Table Background Color ; Referenced Table Horizontal Alignment ; Referenced Table Height Percentage Indicator ; Referenced Table Width Percentage Indicator )

## ***RES\_Parse\_HTbl\_Table***

```
(  
    -> Referenced Resource : Pointer  
    -> Referenced Table Border : Pointer  
    -> Referenced Table Width : Pointer  
    -> Referenced Table Height : Pointer  
    -> Referenced Table Cell Padding : Pointer  
    -> Referenced Table Cell Spacing : Pointer  
    -> Referenced Table Background Color : Pointer  
    -> Referenced Table Horizontal Alignment : Pointer  
    -> Referenced Table Height Percentage Indicator : Pointer  
    -> Referenced Table Width Percentage Indicator : Pointer  
)
```

| <b>Parameter</b>                             | <b>Type</b>    | <b>Description</b>                         |
|--|----------------|--|
| Referenced Resource                          | <b>Pointer</b> | Referenced BLOB containing 'HTbl' resource |
| Referenced Table Border                      | <b>Pointer</b> | not available at this time                 |
| Referenced Table Width                       | <b>Pointer</b> | not available at this time                 |
| Referenced Table Height                      | <b>Pointer</b> | not available at this time                 |
| Referenced Table Cell Padding                | <b>Pointer</b> | not available at this time                 |
| Referenced Table Cell Spacing                | <b>Pointer</b> | not available at this time                 |
| Referenced Table Background Color            | <b>Pointer</b> | not available at this time                 |
| Referenced Table Horizontal Alignment        | <b>Pointer</b> | not available at this time                 |
| Referenced Table Height Percentage Indicator | <b>Pointer</b> | not available at this time                 |
| Referenced Table Width Percentage Indicator  | <b>Pointer</b> | not available at this time                 |

The method *RES\_Parse\_HTbl\_Table* will parse HTML table descriptors from a referenced 'HTbl' resource.

All parameters for this method are not documented at this time. Future versions of the BASH component will fully describe the use of this method.

**Note:** the method *RES\_Parse\_HTbl\_Table* was added in BASH v1.5.5.



## **RES\_Parse\_TMPL**

**RES\_Parse\_TMPL**( *Referenced BLOB*; *Referenced Template Item Titles*;  
*Referenced Template Field Types*) => *Success Indicator*

### **RES\_Parse\_TMPL**

(  
-> *Referenced BLOB*: **Pointer**  
-> *Referenced Template Item Titles*: **Pointer**  
-> *Referenced Template Field Types*: **Pointer**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                       | <b>Type</b>    | <b>Description</b>                                       |
|--|----------------|--|
| <i>Referenced BLOB</i>                 | <b>Pointer</b> | Pointer to BLOB containing 'TMPL' resource to parse      |
| <i>Referenced Template Item Titles</i> | <b>Pointer</b> | Pointer to text array to contain template item titles    |
| <i>Referenced Template Field Types</i> | <b>Pointer</b> | Pointer to longint array to contain template field types |
| <i>Success Indicator</i>               | <b>Longint</b> | qi for parsed successfully                               |

The method *RES\_Parse\_TMPL* will parse a 'TMPL' resource individual pairings of template item titles and template field types.

*Referenced BLOB* is a pointer to a BLOB containing the 'TMPL' resource to parse.

*Referenced Template Item Titles* is a pointer to a text array which will contain the template item titles parsed from the 'TMPL' resource.

*Referenced Template Field Types* is a pointer to a longint array which will contain the template field types parsed from the 'TMPL' resource.

*Success Indicator* is an indicator value for whether the parsing was successful. If *Success Indicator* is zero (0) then the resource was not parsed; if *Success Indicator* is one (1) then the resource was successfully parsed.

**Note:** the method *RES\_Parse\_TMPL* was added in BASH v1.5.1.



## **RES\_Set\_HTbl\_Resource**

**RES\_Set\_HTbl\_Resource** ( *Resource File Reference* ; *Resource ID* ;  
*Referenced Resource* ) => *Success*

### **RES\_Set\_HTbl\_Resource**

(  
    -> *Resource File Reference* : **Time**  
    -> *Resource ID* : **Longint**  
    -> *Referenced Resource* : **Pointer**  
)  
    -> *Success*: **Longint**

| <b>Parameter</b>               | <b>Type</b>    | <b>Description</b>                                    |
|--------------------------------|----------------|---|
| <i>Resource File Reference</i> | <b>Time</b>    | Resource fork file referenced to work with            |
| <i>Resource ID</i>             | <b>Longint</b> | Resource ID to work with                              |
| <i>Referenced Resource</i>     | <b>Pointer</b> | Referenced BLOB to set into indicated 'HTbl' resource |
| <i>Success</i>                 | <b>Longint</b> | qi for set successfully                               |

The method *RES\_Set\_HTbl\_Resource* sets the contents of a 'HTbl' resource within a specified resource document.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Referenced Resource* is a pointer to a BLOB containing the 'HTbl' resource to write to the resource fork of the specified document.

*Success* is an indicator value for whether the setting was successful. If *Success* is zero (0) then the resource was not set; if *Success* is one (1) then the resource was successfully set.

**Note:** the method *RES\_Set-HTbl\_Resource* was added in BASH v1.5.5.



## **RES\_Set\_Resource\_Name**

**RES\_Set\_Resource\_Name**( *Resource Fork File Reference*; *Resource Type*;  
*Resource ID*; *Resource Name*) => *Success Indicator*

### **RES\_Set\_Resource\_Name**

(  
-> *Resource Fork File Reference*: **Time**  
-> *Resource Type*: **Longint**  
-> *Resource ID*: **Longint**  
-> *Resource Name*: **String255**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                    | <b>Type</b>      | <b>Description</b>                        |
|-------------------------------------|------------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>      | Resource fork file reference to work with |
| <i>Resource Type</i>                | <b>Longint</b>   | Resource type to work with                |
| <i>Resource ID</i>                  | <b>Longint</b>   | Resource ID to work with                  |
| <i>Resource Name</i>                | <b>String255</b> | Value to set the resource name to         |
| <i>Success Indicator</i>            | <b>Longint</b>   | qi for set successfully                   |

The method *RES\_Set\_Resource\_Name* set the name of a specified resource in a specified resource document. This method is functionally equivalent to the native 4D command **SET RESOURCE NAME**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource Type* is the resource type to work with.

*Resource ID* is the resource ID to work with.

*Resource Name* is the value to set the specified resource name to.

*Success Indicator* is an indicator value for whether the setting was successful. If *Success Indicator* is zero (0) then the resource was not set; if *Success Indicator* is one (1) then the resource was successfully set.

**Note:** the method *RES\_Set\_Resource\_Name* was added in BASH v1.5.1.



## **RES\_Set\_Resource\_Properties**

***RES\_Set\_Resource\_Properties***( *Resource Fork File Reference*; *Resource Type*;  
*Resource ID*; *Resource Properties*) => *Success Indicator*

### ***RES\_Set\_Resource\_Properties***

```
(  
    -> Resource Fork File Reference: Time  
    -> Resource Type: Longint  
    -> Resource ID: Longint  
    -> Resource Properties: Longint  
)  
=> Success Indicator: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource Type</i>                | <b>Longint</b> | Resource type to work with                |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Resource Properties</i>          | <b>Longint</b> | Value to set the resource properties to   |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for set successfully                   |

The method *RES\_Set\_Resource\_Properties* set the properties of a specified resource in a specified resource document. This method is functionally equivalent to the native 4D command **SET RESOURCE PROPERTIES**.



*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource Type* is the resource type to work with.

*Resource ID* is the resource ID to work with.

*Resource Properties* is the value to set the specified resource properties to.

*Success Indicator* is an indicator value for whether the setting was successful. If *Success Indicator* is zero (0) then the resource was not set; if *Success Indicator* is one (1) then the resource was successfully set.

**Note:** the method *RES\_Set\_Resource\_Properties* was added in BASH v1.5.1.



## **RES\_Set\_TEXT\_Resource**

**RES\_Set\_TEXT\_Resource**( *Resource Fork File Reference*; *Resource ID*;  
*Resource Text Value*) => *Success Indicator*

**RES\_Set\_TEXT\_Resource**  
(  
-> *Resource Fork File Reference*: **Time**  
-> *Resource ID*: **Longint**  
-> *Resource Text Value*: **Text**  
)  
=> *Success Indicator*: **Longint**

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>                        |
|-------------------------------------|----------------|---|
| <i>Resource Fork File Reference</i> | <b>Time</b>    | Resource fork file reference to work with |
| <i>Resource ID</i>                  | <b>Longint</b> | Resource ID to work with                  |
| <i>Resource Text Value</i>          | <b>Text</b>    | Value to set the resource contents to     |
| <i>Success Indicator</i>            | <b>Longint</b> | qi for set successfully                   |

The method *RES\_Set\_TEXT\_Resource* sets the contents of a 'TEXT' resource within a specified resource document. This method is functionally equivalent to the native 4D command **SET TEXT RESOURCE**.

*Resource Fork File Reference* is the reference value to the resource fork of the resource document to work with.

*Resource ID* is the resource ID to work with.

*Resource Text Value* is the contents to set for the specified 'TEXT' resource.

*Success Indicator* is an indicator value for whether the setting was successful. If *Success Indicator* is zero (0) then the resource was not set; if *Success Indicator* is one (1) then the resource was successfully set.

**Note:** the method *RES\_Set\_TEXT\_Resource* was added in BASH v1.5.1.

# SEM Module

The SEM module is the beginning of wrapper functionality for semaphores in 4th Dimension. The current functionality available within the SEM module is fairly limited and may at times seem redundant for what is already available natively within 4th Dimension. But, with future versions of the BASH component, enhancements to the SEM module will be made available.



## SEM\_Clear\_One

**SEM\_Clear\_One** (*Semaphore Name*)

**SEM\_Clear\_One**  
(  
    -> *Semaphore Name*: String [32]  
)

| Parameter             | Type        | Description                |
|-----------------------|-------------|----------------------------|
| <i>Semaphore Name</i> | String [32] | Name of semaphore to clear |

The method **SEM\_Clear\_One** will clear a named semaphore.

The *Semaphore Name* parameter is the name of the semaphore which should be cleared.

This method is equivalent to calling the built in 4th Dimension command **CLEAR SEMAPHORE**. It is recommended that the method **SEM\_Clear\_One** be used in place of **CLEAR SEMAPHORE** though as future enhancements to the SEM module will provide more functionality within this method.



## SEM\_ERROR

**SEM\_ERROR** (*BASH Error Number; Special Error Text; Calling Method Name*)

## **SEM\_ERROR**

```
(  
    -> BASH Error Number: Longint  
    -> Special Error Text: Text  
    -> Calling Method Name: Text  
)
```

| Parameter           | Type    | Description   |
|---------------------|---------|---|
| BASH Error Number   | Longint | Internal BASH error number                              |
| Special Error Text  | Text    | Special text to describe the exact error instance       |
| Calling Method Name | Text    | Name of the method that the error condition occurred in |

The method **SEM\_ERROR** acts as a callback method from within the SEM module for errors that may occur. Any time an error condition is detected within the SEM module, a call to the method **SEM\_ERROR** is made.

The internal *BASH Error Number* is passed to this method as the first parameter. The *Special Error Text* parameter will contain any relevant error text which is specific to the error which occurred. It is not uncommon for the *Special Error Text* value to be empty. The *Calling Method Name* will always contain the name of the SEM method which call the **SEM\_ERROR** method.

The **SEM\_ERROR** method has been implemented as a source for a consistent interface and/or error tracking mechanism to be available while using the BASH component. This method can be modified to suit the needs of the database in which the BASH module has been installed.

**Note:** the method **SEM\_ERROR** was added in BASH v1.5.4.



## **SEM\_Set\_One**

**SEM\_Set\_One** ( Semaphore Name; Ticks Between Checks; Total Ticks to Wait) => Semaphore Status

**SEM\_Set\_One**  
(  
    -> Semaphore Name: **String [32]**  
    -> Ticks Between Checks: **Longint**  
    -> Total Ticks to Wait: **Longint**  
)  
=> Semaphore Status: **Longint**

| Parameter            | Type        | Description  |
|----------------------|-------------|--|
| Semaphore Name       | String [32] | Name of the semaphore to set   |
| Ticks Between Checks | Longint     | Number of ticks to wait between checking for the availability of the semaphore to the current process  |
| Total Ticks to Wait  | Longint     | Total number of ticks to wait for the semaphore in the current process until returning from the method |
| Semaphore Status     | Longint     | Status of attempt to set named semaphore   |

The method **SEM\_Set\_One** is used to set a semaphore from within the current process. It handles checking whether the semaphore is already set, and will wait for it to be cleared for a specified amount of time before setting it within this call or returning without having set it.

The *Semaphore Name* paramater is the name of the semaphore which should be set.

The *Ticks Between Checks* parameter is the number of ticks the method will wait between calls to check whether the named semaphore is available to be set; if the named semaphore is already set, then this method will loop with a delay of *Ticks Between Checks* between each loop waiting for the semaphore to become cleared before setting it within this method. Setting this parameter to zero (0) will product no delay in the loop.

The *Total Ticks to Wait* parameter is the total number of ticks this method will wait for the named semaphore to

become available before it stops trying. If the named semaphore is already set and this method has already waited for *Total Ticks to Wait* for the semaphore to be cleared, the method will return a status code indicating such (see below). If the *Total Ticks to Wait* parameter is set to zero (0), then the named semaphore will be checked for availability only once and set if available; otherwise, no waiting for the named semaphore will be done within this method. If the *Total Ticks to Wait* parameter is set to **MAXLONG** (the native 4th Dimension constant), then this method will wait indefinitely for the named semaphore to become available for setting herein.

The returned parameter *Semaphore Status* indicates the success or failure of this method to set the named semaphore. If *Semaphore Status* is zero (0) then the named semaphore was not set at all. If *Semaphore Status* is one (1) then the named semaphore was successfully set. If *Semaphore Status* is two (2) then the named semaphore was not set because it was already set from another location and did not become available within the time allowed to this method.

It is recommended that the method **SEM\_Set\_One** be used in place of the 4th Dimension **SEMAPHORE** command as future enhancements to the SEM module will provide more functionality within this method. In any case, the **SEM\_Set\_One** method provides more functionality than is available by the native **SEMAPHORE** command.



## **SEM\_Test\_One**

**SEM\_Test\_One** ( *Named Semaphore* ) => *Semaphore Status*

```
SEM_Test_One
(
    -> Named Semaphore : String [32]
)
=> Semaphore Status : Longint
```

| Parameter | Type | Description |
|-----------|------|-------------|
|-----------|------|-------------|

|                         |             |   |
|-------------------------|-------------|---|
| <i>Named Semaphore</i>  | String [32] | Name of semaphore to check                |
| <i>Semaphore Status</i> | Longint     | qi for whether semaphore is currently set |

The method *SEM\_Test\_One* will return the status of a named semaphore.

*Named Semaphore* is the name of a semaphore to check the status of.

*Semaphore Status* is qi for whether the *Named Semaphore* is currently set. *Semaphore Status* will be set to one (1) if *Named Semaphore* is currently set; *Semaphore Status* will be set to zero (0) if *Named Semaphore* is not currently set.

**Note:** the method *SEM\_Test\_One* was added in BASH v1.5.4.

## SERNO Module

The SERNO module is useful for serializing applications or functionality within an application. It provides for encoded storage locations within the serial numbers generated for a product code, user count, major and minor versions, beta flag, and year and month expiration dates.

The routines in the SERNO module merely provide a mechanism for generating and decoding serial numbers. The actions a particular application are to take with respect to serial numbers is determined by the developer.

The serial numbers created by the SERNO module are twenty (20) byte strings of alphanumeric values. All serial numbers are case sensitive. And, it is a simple enough matter to format serial numbers with embedded hyphens for easier handling by users.

The data contained in generated serial numbers is encoded across all of the byte values within the serial number. No particular byte value corresponds to any single serial number parameters, thereby assuring reasonable security for application developers. Also, random bytes of data are spread throughout the contents of generated serial numbers and checksums are inherently encoded, as well.

Greater security for serial numbers can be had by combining the SERNO module methods with the CRYPT module and CODEC module. The CRYPT module can be used to provide a 128 bit encryption on top of a serial number and the CODEC module can then encode the encrypted serial number so that it is still easily handled by users.

There are limitations to the numerical values of all parameters encoded within a serial number. The following table lists the valid value ranges for each value encoded in a serial number:

| <u>Parameter</u> | <u>Low</u> | <u>High</u> |
|------------------|------------|-------------|
|------------------|------------|-------------|



|               |     |       |
|---------------|-----|-------|
| Product Code  | 0   | 63    |
| Users         | 0   | 65535 |
| Major Version | 0   | 63    |
| Minor Version | 0   | 63    |
| Beta Flag     | n/a | n/a   |
| Month         | 0   | 16    |
| Year          | 0   | 16    |

Keep in mind, though the different parameter values are named particularly, these names are merely for convenience in documentation and referencing. In essence, the different values are named arbitrarily and can be treated as such. So, the developer chooses completely the effect each parameter, and its values, have upon the application they are being used within.

**Note:** the SERNO module was initially added in BASH v1.5.5.



## **SERNO\_Create\_SerialNumber**

**SERNO\_Create\_SerialNumber** ( *Product Code ; Users ; Major Version ; Minor Version ; Beta Flag ; Month ; Year* ) => *Serial Number*

**SERNO\_Create\_SerialNumber**

```
(
    -> Product Code : Longint
    -> Users : Longint
    -> Major Version : Longint
    -> Minor Version : Longint
    -> Beta Flag : Boolean
    -> Month : Longint
    -> Year : Longint
)
=> Serial Number : Text
```

| <b>Parameter</b>     | <b>Type</b> | <b>Description</b>                 |
|----------------------|-------------|------------------------------------|
| <i>Product Code</i>  | Longint     | Unique identifier code for product |
| <i>Users</i>         | Longint     | Number of users                    |
| <i>Major Version</i> | Longint     | Major version number for product   |
| <i>Minor Version</i> | Longint     | Minor version number for product   |

|                      |         |   |
|----------------------|---------|---|
| <i>Beta Flag</i>     | Boolean | Flag to indicate beta version for product                           |
| <i>Month</i>         | Longint | Expiration month for product  |
| <i>Year</i>          | Longint | Expiration Year for product   |
| <i>Serial Number</i> | Text    | Generated serial number containing discrete data elements specified |

The method *SERNO\_Create\_SerialNumber* will generate a serial number from the values provided. Subsequent calls to this method will produce different serial numbers each time even with the parameters remaining the same. All parameters are encoded into the serial number and can be extracted later using the other methods in the SERNO module.

*Product Code* is the product code to encode into the generated serial number.

*Users* is the user count to encode into the generated serial number.

*Major Version* is the major version code to encode into the generated serial number.

*Minor Version* is the minor version code to encode into the generated serial number.

*Beta Flag* is the boolean beta flag to encode into the generated serial number.

*Month* is the expiration month value to encode into the generated serial number.

*Year* is the expiration year value to encode into the generated serial number.

*Serial Number* is the twenty (20) byte serial number randomly generated containing the encoded parameters provided.

**Note:** the method *SERNO\_Create\_SerialNumber* was added in BASH v1.5.5.



## **SERNO\_Decode\_SerialNumber**

**SERNO\_Decode\_SerialNumber** ( *Serial Number* ; *Referenced Product Code* ; *Referenced Users* ; *Referenced Major Version* ; *Referenced Minor Version* ; *Referenced Beta Flag* ; *Referenced Month* ; *Referenced Year* ) => *Valid Serial Flag*

### **SERNO\_Decode\_SerialNumber**

```
(  
    -> Serial Number : Text  
    -> Referenced Product Code : Pointer  
    -> Referenced Users : Pointer  
    -> Referenced Major Version : Pointer  
    -> Referenced Minor Version : Pointer  
    -> Referenced Beta Flag : Pointer  
    -> Referenced Month : Pointer  
    -> Referenced Year : Pointer  
)  
=> Valid Serial Flag : Boolean
```

| <b>Parameter</b>                | <b>Type</b>    | <b>Description</b>                                   |
|---------------------------------|----------------|--|
| <i>Serial Number</i>            | <b>Text</b>    | Serial number to decode                              |
| <i>Referenced Product Code</i>  | <b>Pointer</b> | Referenced longint to hold product code              |
| <i>Referenced Users</i>         | <b>Pointer</b> | Referenced longint to hold users                     |
| <i>Referenced Major Version</i> | <b>Pointer</b> | Referenced longint to hold major version             |
| <i>Referenced Minor Version</i> | <b>Pointer</b> | Referenced longint to hold minor version             |
| <i>Referenced Beta Flag</i>     | <b>Pointer</b> | Referenced boolean to hold beta flag                 |
| <i>Referenced Month</i>         | <b>Pointer</b> | Referenced longint to hold expiration month          |
| <i>Referenced Year</i>          | <b>Pointer</b> | Referenced longint to hold expiration year           |
| <i>Valid Serial Flag</i>        | <b>Boolean</b> | q for whether serial number is valid and well formed |

The method **SERNO\_Decode\_SerialNumber** will decode a serial number and return the values in referenced parameters.

*Serial Number* is the twenty (20) byte serial number to decode.

*Referenced Product Code* is a pointer to a longint to contain the product code decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

*Referenced Users* is a pointer to a longint to contain the user count decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

*Referenced Major Version* is a pointer to a longint to contain the major version code decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

*Referenced Minor Version* is a pointer to a longint to contain the minor version code decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

*Referenced Beta Flag* is a pointer to a boolean to contain the beta flag to decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

*Referenced Month* is a pointer to a longint to contain the expiration month value decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

*Referenced Year* is a pointer to a longint to contain the expiration year value decoded and extracted from *Serial Number* . The parameter can be passed a NULL value to skip.

**Note:** the method *SERNO\_Decode\_SerialNumber* was added in BASH v1.5.5.



## **SERNO\_Get\_Beta**

**SERNO\_Get\_Beta** ( *Serial Number* ) => *Beta Flag*

## **SERNO\_Get\_Beta**

```
(  
    -> Serial Number : Text  
)  
=> Beta Flag : Boolean
```

| Parameter     | Type    | Description                                   |
|---------------|---------|---|
| Serial Number | Text    | Serial number to decode                       |
| Beta Flag     | Boolean | Beta flag contained in supplied serial number |

The method **SERNO\_Get\_Beta** will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Beta Flag* is the beta flag decoded and extracted from *Serial Number*.

**Note:** the method **SERNO\_Get\_Beta** was added in BASH v1.5.5.



## **SERNO\_Get\_MajorVersion**

**SERNO\_Get\_MajorVersion** ( *Serial Number* ) => *Major Version*

### **SERNO\_Get\_MajorVersion**

```
(  
    -> Serial Number : Text  
)  
=> Major Version : Longint
```

| Parameter     | Type    | Description                                       |
|---------------|---------|---|
| Serial Number | Text    | Serial number to decode                           |
| Major Version | Longint | Major version contained in supplied serial number |

The method **SERNO\_Get\_MajorVersion** will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Major Version* is the major version value decoded and extracted from *Serial Number* .

**Note:** the method *SERNO\_Get\_MajorVersion* was added in BASH v1.5.5.



## **SERNO\_Get\_MinorVersion**

**SERNO\_Get\_MinorVersion** (*Serial Number* ) => *Minor Version*

**SERNO\_Get\_MinorVersion**

```
(  
    -> Serial Number : Text  
)  
=> Minor Version : Longint
```

| Parameter            | Type    | Description                                       |
|----------------------|---------|---|
| <i>Serial Number</i> | Text    | Serial number to decode                           |
| <i>Minor Version</i> | Longint | Minor version contained in supplied serial number |

The method *SERNO\_Get\_MinorVersion* will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Minor Version* is the minor version value decoded and extracted from *Serial Number* .

**Note:** the method *SERNO\_Get\_MinorVersion* was added in BASH v1.5.5.



## **SERNO\_Get\_Month**

**SERNO\_Get\_Month** (*Serial Number* ) => *Month*

## **SERNO\_Get\_Month**

```
(  
    -> Serial Number : Text  
)  
=> Month : Longint
```

| Parameter            | Type    | Description  |
|----------------------|---------|--|
| <i>Serial Number</i> | Text    | Serial number to decode                              |
| <i>Month</i>         | Longint | Expiration month contained in supplied serial number |

The method **SERNO\_Get\_Month** will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Month* is the expiration month value decoded and extracted from *Serial Number*.

**Note:** the method **SERNO\_Get\_Month** was added in BASH v1.5.5.



## **SERNO\_Get\_ProductCode**

**SERNO\_Get\_ProductCode** (*Serial Number*) => *Product Code*

### **SERNO\_Get\_ProductCode**

```
(  
    -> Serial Number : Text  
)  
=> Product Code : asd
```

| Parameter            | Type    | Description                                      |
|----------------------|---------|--|
| <i>Serial Number</i> | Text    | Serial number to decode                          |
| <i>Product Code</i>  | Longint | Product code contained in supplied serial number |

The method **SERNO\_Get\_ProductCode** will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Product Code* is the product code value decoded and extracted from *Serial Number* .

**Note:** the method *SERNO\_Get\_ProductCode* was added in BASH v1.5.5.



## **SERNO\_Get\_Users**

**SERNO\_Get\_Users** ( *Serial Number* ) => *Users*

**SERNO\_Get\_Users**

```
(  
    -> Serial Number :Text  
)  
=> Users :asd
```

| Parameter            | Type    | Description                               |
|----------------------|---------|---|
| <i>Serial Number</i> | Text    | Serial number to decode                   |
| <i>Users</i>         | Longint | Users contained in supplied serial number |

The method *SERNO\_Get\_Users* will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Users* is the user count value decoded and extracted from *Serial Number* .

**Note:** the method *SERNO\_Get\_Users* was added in BASH v1.5.5.



## **SERNO\_Get\_Year**

**SERNO\_Get\_Year** ( *Serial Number* ) => *Year*



### ***SERNO\_Get\_Year***

```
(  
    -> Serial Number : Text  
)  
=> Year : asd
```

| <b>Parameter</b>     | <b>Type</b> | <b>Description</b>                                  |
|----------------------|-------------|---|
| <i>Serial Number</i> | Text        | Serial number to decode                             |
| <i>Year</i>          | Longint     | Expiration year contained in supplied serial number |

The method ***SERNO\_Get\_Year*** will decode a serial number and return a particular encoded parameter within it.

*Serial Number* is the twenty (20) byte serial number to decode.

*Year* is the expiration year value decoded and extracted from *Serial Number* .

**Note:** the method ***SERNO\_Get\_Year*** was added in BASH v1.5.5.

# STR Module

The STR module provides numerous methods for manipulating text and string values. The methods in the STR module comprise many basic and common operations which are performed on text values. As with many of the modules in the BASH component, this module will be continuously growing with future releases.

**Note:** the STR module was initially added in BASH v1.5.1.



## **STR\_Clean\_EmailAddress**

**STR\_Clean\_EmailAddress**( *Text Value* ) => *Cleansed Text Value*

**STR\_Clean\_EmailAddress**

(  
    -> *Text Value: Text*  
)  
    => *Cleansed Text Value: Text*

| Parameter                  | Type | Description         |
|----------------------------|------|---------------------|
| <i>Text Value</i>          | Text | Text value to clean |
| <i>Cleansed Text Value</i> | Text | Cleansed text value |

The method **STR\_Clean\_EmailAddress** will removed all invalid byte values for a properly comprised email address.

Valid values for email addresses include: uppercase letters, lowercase letters, numbers, hyphen, period, underscore, and the at sign. All other byte values are consider invalid and will be removed with this method.

*Text Value* is the supplied text value to be cleansed.

*Cleansed Text Value* is *Text Value* with all invalid email address bytes removed.

Note: the method *STR\_Clean\_EmailAddress* was added in BASH v1.5.1.

---

## **STR\_Clean\_EmailUsername**

**STR\_Clean\_EmailUsername** ( *Text Value* ) => *Cleansed Text Value*

**STR\_Clean\_EmailUsername**  
(  
    -> *Text Value: Text*  
)  
=> *Cleansed Text Value: Text*

| Parameter                  | Type | Description         |
|----------------------------|------|---------------------|
| <i>Text Value</i>          | Text | Text value to clean |
| <i>Cleansed Text Value</i> | Text | Cleansed text value |

The method *STR\_Clean\_EmailUsername* will removed all invalid byte values for a properly comprised email username.

Valid values for email username include: uppercase letters, lowercase letters, numbers, hyphen, period, and underscore. All other byte values are consider invalid and will be removed with this method.

*Text Value* is the supplied text value to be cleansed.

*Cleansed Text Value* is *Text Value* with all invalid email username bytes removed.

Note: the method *STR\_Clean\_EmailUsername* was added in BASH v1.5.3.

---

## **STR\_Concatenate\_Text**

**STR\_Concatenate\_Text**( *Referenced Concatenated Text; Overflow Option*{;*Referenced Text Value*{; ...}}) => *Byte Count*

## ***STR\_Concatenate\_Text***

```
(  
    -> Referenced Concatenated Text: Pointer  
    -> Overflow Option: Longint  
    {-> Referenced Text Value: Pointer}  
)  
=> Byte Count: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>   |
|-------------------------------------|----------------|--|
| <i>Referenced Concatenated Text</i> | <b>Pointer</b> | Pointer to text variable to hold concatenated text               |
| <i>Overflow Option</i>              | <b>Longint</b> | Overflow option setting  |
| <i>Referenced Text Value</i>        | <b>Pointer</b> | One or more pointer to text values to concatenate                |
| <i>Byte Count</i>                   | <b>Longint</b> | Number of bytes in resulting <i>Referenced Concatenated Text</i> |

The method ***STR\_Concatenate\_Text*** concatenates multiple referenced text values while properly respecting overflow limitations. An overflow option setting determines whether concatenation is performed up to the overflow state in the event that concatenation would normally produce an overflow condition.

This method provides a fullproof means to concatenate text values and avoid possible overflow conditions. This is essential for many unattended systems which must run continuously in an error and dialog free state.

*Referenced Concatenated Text* is a pointer to a text variable which will contain the concatenated text values. Depending on the value of *Overflow Option* and potential overflow conditions, *Referenced Concatenated Text* may actually be empty.

*Overflow Option* is an indicator setting for what this method will do in the even that the concatenation of the *Referenced Text Value* parameters' values would product an overflow condition. If *Overflow Option* is zero (0) then *Referenced Concatenated Text* will be empty in the event of a possible overflow. If *Overflow Option* is one (1) then *Referenced Concatenated Text* will be the first MAXTEXTLEN bytes of the concatenation of the

*Referenced Text Value* parameters' values; the remaining overflow text will be truncated.

*Referenced Text Value* is between one (1) and fourteen (14) pointers to text variables which will be concatenated within this method. The referenced values are concatenated in the order of the parameter references.

*Byte Count* contains the total number of bytes within *Referenced Concatenated Text* upon returning from this method.

**Note:** the method *STR\_Concatenate\_Text* was added in BASH v1.5.1.



## **STR\_Count\_Occurrences\_of\_ASCII**

**STR\_Count\_Occurrences\_of\_ASCII**( *Text Value*; *ASCII Value*) =>  
*Occurrence Count*

**STR\_Count\_Occurrences\_of\_ASCII**  
(  
    -> *Text Value*: **Text**  
    -> *ASCII Value*: **Longint**  
)  
=> *Occurrence Count*: **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>  |
|-------------------------|----------------|---|
| <i>Text Value</i>       | <b>Text</b>    | Text value to scan  |
| <i>ASCII Value</i>      | <b>Longint</b> | ASCII value of bytes to count                                       |
| <i>Occurrence Count</i> | <b>Longint</b> | Count of occurrences of <i>ASCII Value</i> within <i>Text Value</i> |

The method *STR\_Count\_Occurrences\_of\_ASCII* will count the number of occurrences of a specified ASCII value within a block of text.

For single byte scanning, this method is much faster than the method *STR\_Count\_Occurrences\_of\_String*.

*Text Value* is the text block to scan.

*ASCII Value* is the ASCII value to actually scan for within *Text Value*.

*Occurrence Count* is the total number of occurrences of the *ASCII Value* within the text block *Text Value*.

**Note:** the method *STR\_Count\_Occurrences\_of\_ASCII* was added in BASH v1.5.1.



## **STR\_Count\_Occurrences\_of\_String**

**STR\_Count\_Occurrences\_of\_String**( *Text Value*; *Match Text*) => *Occurrence Count*

**STR\_Count\_Occurrences\_of\_String**  
(  
    -> *Text Value*: **Text**  
    -> *Match Text*: **Text**  
)  
=> *Occurrence Count*: **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>   |
|-------------------------|----------------|--|
| <i>Text Value</i>       | <b>Text</b>    | Text value to scan   |
| <i>Match Text</i>       | <b>Text</b>    | Text value to match for counting                                   |
| <i>Occurrence Count</i> | <b>Longint</b> | Count of occurrences of <i>Match Text</i> within <i>Text Value</i> |

The method *STR\_Count\_Occurrences\_of\_String* will count the number of occurrences of a specified match text value within a block of text. The string matching is done using native 4D string comparison operators and comparators and is inclusive for multiple match values within and overlapping match strings.

For single byte scanning, the method *STR\_Count\_Occurrences\_of\_ASCII* is much faster for counting occurrences.

*Text Value* is the text block to scan.

*Match Text* is the actual match string to scan for within *Text Value*.

*Occurrence Count* is the total number of occurrences of the *Match Text* within the text block *Text Value*.

**Note:** the method *STR\_Count\_Occurrences\_of\_String* was added in BASH v1.5.1.



## **STR\_Get\_CharPosition\_by\_ASCII**

**STR\_Get\_CharPosition\_by\_ASCII**( *Text Value*; *ASCII Value*; *Start Byte*;  
*Direction Option*) => *Found Byte*

**STR\_Get\_CharPosition\_by\_ASCII**  
(  
    -> *Text Value*: **Text**  
    -> *ASCII Value*: **Longint**  
    -> *Start Byte*: **Longint**  
    -> *Direction Option*: **Longint**  
)  
=> *Found Byte*: **Longint**

| <b>Parameter</b>        | <b>Type</b>    | <b>Description</b>   |
|-------------------------|----------------|--|
| <i>Text Value</i>       | <b>Text</b>    | Text value to scan   |
| <i>ASCII Value</i>      | <b>Longint</b> | ASCII value of byte to scan for  |
| <i>Start Byte</i>       | <b>Longint</b> | Starting byte position within <i>Text Value</i>                                    |
| <i>Direction Option</i> | <b>Longint</b> | Direction option for whether to scan forward or backwards within <i>Text Value</i> |
| <i>Found Byte</i>       | <b>Longint</b> | Byte position of first byte within <i>Text Value</i> matching scanning options     |

The method *STR\_Get\_CharPosition\_by\_ASCII* returns the byte position of the first byte found within a specified text block matching a particular value. This byte can be scanned for either forward or backwards from any starting byte position within the specified text block.

*Text Value* is the text block to scan.

*ASCII Value* is the ASCII value to actually scan for within *Text Value*.

*Start Byte* is the starting byte position to begin the scanning from.

*Direction Option* is the looping parameter for which direction to scan for the matching byte value within *Text Value*. If *Direction Option* is one (1) then the scanning is done forward through *Text Value* starting at *Start Byte*. If *Direction Option* is negative one (-1) then the scanning is done backwards through *Text Value* starting at *Start Byte*.

*Found Byte* is the position of the first occurrence of *ASCII Value* found within *Text Value* when using the specified scanning options within this method. The following table summarizes result values for *Found Byte* after calling this method:

| <u>Found Byte value</u> | <u>Indicates</u>                      |
|-------------------------|---------------------------------------|
| > 0                     | position of next match                |
| 0                       | no match found                        |
| - 1                     | text block to scan is empty           |
| - 2                     | ASCII value invalid                   |
| - 3                     | start byte is too high (out of range) |

**Note:** since *Direction Option* is actually the looping parameter within this method, scanning can be done on everything *nth* byte if the need arises. There are no limitations within this method to prevent different integral values, both positive and negative, from being passed to this method. Positive values will scan forward and negative values will scan backwards.

**Note:** the method *STR\_Get\_CharPosition\_by\_ASCII* was added in BASH v1.5.1.



## **STR\_Get\_Line\_First**

**STR\_Get\_Line\_First**( *Text Value* ) => *First Line Text*



## **STR\_Get\_Line\_First**

```
(  
    -> Text Value: Text  
)  
=> First Line Text: Text
```

| Parameter       | Type | Description                          |
|-----------------|------|--------------------------------------|
| Text Value      | Text | Text block to scan                   |
| First Line Text | Text | Text of first line within Text Value |

The method **STR\_Get\_Line\_First** will return the first line within a specified text block. Lines of text are considered to be delimited by carriage returns (ASCII value 13) within this method.

*Text Value* is the text block to scan.

*First Line Text* is the text of the first line within *Text Value*. If no carriage returns are found within *Text Value* then *First Line Text* is set to the complete *Text Value*.

**Note:** the method **STR\_Get\_Line\_First** was added in BASH v1.5.1.



## **STR\_Pad\_String**

**STR\_Pad\_String**( Referenced Text Value; Preferred Length; ASCII Value; Padding Flag)

### **STR\_Pad\_String**

```
(  
    -> Referenced Text Value: Pointer  
    -> Preferred Length: Longint  
    -> ASCII Value: Longint  
    -> Padding Flag: Boolean  
)
```

| Parameter             | Type    | Description                                       |
|-----------------------|---------|---|
| Referenced Text Value | Pointer | Pointer to text value to pad                      |
| Preferred Length      | Longint | Preferred minimum length of Referenced Text Value |
| ASCII Value           | Longint | ASCII value of bytes used for padding             |

|                     |                |   |
|---------------------|----------------|---|
| <i>Padding Flag</i> | <b>Boolean</b> | <b>Flag for whether padding goes after string or before</b> |
|---------------------|----------------|---|

The method ***STR\_Pad\_String*** will pad out a referenced text value to always be a minimum length. This method is ideal for providing formatting columnar data.

*Referenced Text Value* is a pointer to the text value to pad to a minimum length.

*Preferred Length* is the minimum length required for *Referenced Text Value*. If the length of *Referenced Text Value* is less than *Preferred Length* then it will be padded to this minimum length. If the length of *Referenced Text Value* is greater than *Preferred Length* then no change will be made to *Referenced Text Value*.

*ASCII Value* is the ASCII value to use for any padding bytes which are added to *Referenced Text Value*.

*Padding Flag* is a boolean value for whether padding bytes added should be done after *Referenced Text Value*. If *Padding Flag* is not set then padding bytes will be added before *Referenced Text Value*, if length requirements deem it necessary..

**Note:** the method ***STR\_Pad\_String*** was added in BASH v1.5.1.



## **STR\_Parse\_to\_Array\_by\_ASCII**

***STR\_Parse\_to\_Array\_by\_ASCII***( *Referenced Text Array*; *Text Value*;  
*Delimiter ASCII Value*) => *Element Count*

***STR\_Parse\_to\_Array\_by\_ASCII***  
 (  
     -> *Referenced Text Array*: **Pointer**  
     -> *Text Value*: **Text**  
     -> *Delimiter ASCII Value*: **Longint**  
 )  
     => *Element Count*: **Longint**

| Parameter                    | Type    | Description   |
|------------------------------|---------|---|
| <i>Referenced Text Array</i> | Pointer | Pointer to text array to hold parsed values             |
| <i>Text Value</i>            | Text    | Text block to parse                                     |
| <i>Delimiter ASCII Value</i> | Longint | ASCII value of value delimiter within <i>Text Value</i> |
| <i>Element Count</i>         | Longint | Number of elements parsed from <i>Text Value</i>        |

The method ***STR\_Parse\_to\_Array\_by\_ASCII*** will parse a text block into one or more elements. The elements can be separate within the text block by any ASCII value.

For single byte delimiters, this method is much faster than the method ***STR\_Parse\_to\_Array\_by\_Str***.

*Referenced Text Array* is a pointer to a text array that will hold the parsed values.

*Text Value* is the text block to parse.

*Delimiter ASCII Value* is the ASCII value of the value delimiter within *Text Value*.

*Element Count* is the number of elements parsed from *Text Value*. The following table summarizes possible values for the *Element Count* return value:

| <u>Found Byte value</u> | <u>Indicates</u>                |
|-------------------------|---------------------------------|
| > 0                     | element count                   |
| - 1                     | referencing not to a text array |
| - 2                     | no reference parameter          |

**Note:** the method ***STR\_Parse\_to\_Array\_by\_ASCII*** was added in BASH v1.5.1.



## **STR\_Parse\_to\_Array\_by\_Str**

***STR\_Parse\_to\_Array\_by\_Str***( *Referenced Text Array*; *Text Value*; *Delimiter Text*) => *Element Count*

***STR\_Parse\_to\_Array\_by\_Str***

```
(
    -> Referenced Text Array: Pointer
    -> Text Value: Text
    -> Delimiter Text: Text
)
=> Element Count: Longint
```

| <b>Parameter</b>             | <b>Type</b>    | <b>Description</b>                               |
|------------------------------|----------------|--|
| <i>Referenced Text Array</i> | <b>Pointer</b> | Pointer to text array to hold parsed values      |
| <i>Text Value</i>            | <b>Text</b>    | Text block to parse                              |
| <i>Delimiter Text</i>        | <b>Text</b>    | Text value of delimiter within <i>Text Value</i> |
| <i>Element Count</i>         | <b>Longint</b> | Number of elements parsed from <i>Text Value</i> |

The method *STR\_Parse\_to\_Array\_by\_Str* will parse a text block into one or more elements. The elements can be separate within the text block by any text value. Delimiter matches are determined by using native 4D string operators and comparators.

For single byte delimiters, the method *STR\_Parse\_to\_Array\_by\_ASCII* is much faster and efficient.

*Referenced Text Array* is a pointer to a text array that will hold the parsed values.

*Text Value* is the text block to parse.

*Delimiter Text* is the text value of the value delimiter within *Text Value*.

*Element Count* is the number of elements parsed from *Text Value*. The following table summarizes possible values for the *Element Count* return value:

| <u>Found Byte value</u> | <u>Indicates</u>                 |
|-------------------------|----------------------------------|
| > 0                     | element count                    |
| - 1                     | referencing not to a text array  |
| - 2                     | no reference parameter           |
| - 3                     | delimiter longer than text block |

Note: the method *STR\_Parse\_to\_Array\_by\_Str* was added in BASH v1.5.1.



## **STR\_Position\_NonAlpha**

**STR\_Position\_NonAlpha** ( *Text Value* ; *Starting Position* ; *Byte Count* ) =>  
*Found Position*

**STR\_Position\_NonAlpha**  
(  
    -> *Text Value* : **Text**  
    -> *Starting Position* : **Longint**  
    -> *Byte Count* : **Longint**  
)  
=> *Found Position* : **Longint**

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>                                 |
|--------------------------|----------------|--|
| <i>Text Value</i>        | <b>Text</b>    | Text to scan                                       |
| <i>Starting Position</i> | <b>Longint</b> | Starting position in text to begin scanning from   |
| <i>Byte Count</i>        | <b>Longint</b> | Maximum number of bytes within text to scan        |
| <i>Found Position</i>    | <b>Longint</b> | Position within text of first non-alpha byte found |

The method *STR\_Position\_NonAlpha* returns the first byte position within a specified range of a specified text value which is not a standard ASCII character value.

*Text Value* is the text which is to be scanned.

*Starting Position* is the first byte position within *Text Value* which is to be scanned.

*Byte Count* is the maximum number of bytes to scan after *Starting Position* within *Text Value* . No bytes after will be scanned. To always scan to the end of *Text Value* , pass a value of MaxLong for *Byte Count* .

*Found Position* is the first position within *Text Value* after *Starting Position* which contains a non-alpha value. If there are no bytes found within the specified

range which are non-alpha, *Found Position* will be set to zero (0).

**Note:** the method *STR\_Position\_NonAlpha* was added in BASH v1.5.7.



## **STR\_Position\_NonAlphaNumeric**

**STR\_Position\_NonAlphaNumeric** ( *Text Value* ; *Starting Position* ; *Byte Count* ) => *Found Position*

**STR\_Position\_NonAlphaNumeric**  
(  
    -> *Text Value* : **Text**  
    -> *Starting Position* : **Longint**  
    -> *Byte Count* : **Longint**  
)  
    => *Found Position* : **Longint**

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>  |
|--------------------------|----------------|---|
| <i>Text Value</i>        | <b>Text</b>    | Text to scan  |
| <i>Starting Position</i> | <b>Longint</b> | Starting position in text to begin scanning from          |
| <i>Byte Count</i>        | <b>Longint</b> | Maximum number of bytes within text to scan               |
| <i>Found Position</i>    | <b>Longint</b> | Position within text of first non-alphanumeric byte found |

The method *STR\_Position\_NonAlphaNumeric* returns the first byte position within a specified range of a specified text value which is not a standard ASCII character or numeral value.

*Text Value* is the text which is to be scanned.

*Starting Position* is the first byte position within *Text Value* which is to be scanned.

*Byte Count* is the maximum number of bytes to scan after *Starting Position* within *Text Value* . No bytes after will be scanned. To always scan to the end of *Text Value* , pass a value of MaxLong for *Byte Count* .

*Found Position* is the first position within *Text Value* after *Starting Position* which contains a non-alphanumeric value. If there are no bytes found within the specified range which are non-alphanumeric, *Found Position* will be set to zero (0).

**Note:** the method *STR\_Position\_NonAlphaNumeric* was added in BASH v1.5.7.



## **STR\_Position\_NonNumeric**

**STR\_Position\_NonNumeric** ( *Text Value* ; *Starting Position* ; *Byte Count* )  
=> *Found Position*

**STR\_Position\_NonNumeric**  
(  
-> *Text Value* : **Text**  
-> *Starting Position* : **Longint**  
-> *Byte Count* : **Longint**  
)  
=> *Found Position* : **Longint**

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>  |
|--------------------------|----------------|---|
| <i>Text Value</i>        | <b>Text</b>    | Text to scan  |
| <i>Starting Position</i> | <b>Longint</b> | Starting position in text to begin scanning from          |
| <i>Byte Count</i>        | <b>Longint</b> | Maximum number of bytes within text to scan               |
| <i>Found Position</i>    | <b>Longint</b> | Position within text of first non-alphanumeric byte found |

The method *STR\_Position\_NonNumeric* returns the first byte position within a specified range of a specified text value which is not a standard ASCII numeral value.

*Text Value* is the text which is to be scanned.

*Starting Position* is the first byte position within *Text Value* which is to be scanned.

*Byte Count* is the maximum number of bytes to scan after *Starting Position* within *Text Value* . No bytes

after will be scanned. To always scan to the end of *Text Value* , pass a value of MaxLong for *Byte Count* .

*Found Position* is the first position within *Text Value* after *Starting Position* which contains a non-numeric value. If there are no bytes found within the specified range which are non-numeric, *Found Position* will be set to zero (0).

**Note:** the method *STR\_Position\_NonNumeric* was added in BASH v1.5.7.



## **STR\_qi\_Match\_Filter\_NonCase**

**STR\_qi\_Match\_Filter\_NonCase**( *Source Text Value*; *Filter*; *Multiple Wilcard ASCII Value*; *Single Wilcard ASCII Value*) => *Match Successful*

**STR\_qi\_Match\_Filter\_NonCase**

```
(  
    -> Source Text Value: Text  
    -> Filter: Text  
    -> Multiple Wilcard ASCII Value: Longint  
    -> Single Wilcard ASCII Value: Longint  
)  
=> Match Successful: Longint
```

| <b>Parameter</b>                    | <b>Type</b>    | <b>Description</b>   |
|-------------------------------------|----------------|--|
| <i>Source Text Value</i>            | <b>Text</b>    | Text to compare with a particular filter and filter criteria                         |
| <i>Filter</i>                       | <b>Text</b>    | Filter to compare against <i>Source Text Value</i>                                   |
| <i>Multiple Wilcard ASCII Value</i> | <b>Longint</b> | ASCII value of multiple wildcard byte within <i>Filter</i>                           |
| <i>Single Wilcard ASCII Value</i>   | <b>Longint</b> | ASCII value of single wildcard byte within <i>Filter</i>                             |
| <i>Match Successful</i>             | <b>Longint</b> | qi for whether <i>Source Text Value</i> matches specified filter and filter criteria |

The method *STR\_qi\_Match\_Filter\_NonCase* will return an indicator for whether a specified text block matches a specified filter string. The single and



multiple wildcard values are specified as parameters into this method.

Comparisons are done using standard 4D operators and comparators, though wildcard byte matches must be exact.

*Source Text Value* is the text value to compare for matching a specified filter and filter criteria.

*Filter* is the filter string to use for comparison against *Source Text Value*. *Filter* can contain zero, one, or more than one of both multiple and single wildcard values.

*Multiple Wildcard ASCII Value* is the ASCII value of the multiple wildcard value used within *Filter*.

*Single Wildcard ASCII Value* is the ASCII value of the single wildcard value used within *Filter*.

*Match Successful* is an indicator value for whether *Source Text Value* matches the specified filter and filter criteria.

**Note:** the method *STR\_qi\_Match\_Filter\_NonCase* was added in BASH v1.5.1.



## **STR\_Remove\_After\_Last\_by\_ASCII**

**STR\_Remove\_After\_Last\_by\_ASCII**( *Text Value*; *Delimiter ASCII Value*)  
=> *Truncated Text Value*

**STR\_Remove\_After\_Last\_by\_ASCII**  
(  
-> *Text Value*: **Text**  
-> *Delimiter ASCII Value*: **Longint**  
)  
=> *Truncated Text Value*: **Text**

| <b>Parameter</b>  | <b>Type</b> | <b>Description</b>     |
|-------------------|-------------|------------------------|
| <i>Text Value</i> | <b>Text</b> | Text block to truncate |

|                              |                |                               |
|------------------------------|----------------|-------------------------------|
| <i>Delimiter ASCII Value</i> | <b>Longint</b> | ASCII value to truncate after |
| <i>Truncated Text Value</i>  | <b>Text</b>    | Truncated text block          |

The method ***STR\_Remove\_After\_Last\_by\_ASCII*** will truncate a specified text block after the *last* occurrence of a specified byte value.

*Text Value* is the text block to be scanned and truncated.

*Delimiter ASCII Value* is the ASCII value of the byte which will be truncated after. The last occurrence of *Delimiter ASCII Value* within *Text Value* will be the last byte returned in *Truncated Text Value*.

*Truncated Text Value* is the resulting truncated text. If the *Delimiter ASCII Value* is invalid then the complete *Text Value* will be returned. If the *Delimiter ASCII Value* is not found within *Text Value* then the value returned in *Truncated Text Value* will be empty.

**Note:** the method ***STR\_Remove\_After\_Last\_by\_ASCII*** was added in BASH v1.5.1.



## **STR\_Remove\_Line\_First**

***STR\_Remove\_Line\_First***( *Text Value*) => *Truncated Text Value*

```
STR_Remove_Line_First
(
    -> Text Value: Text
)
=> Truncated Text Value: Text
```

| <b>Parameter</b>            | <b>Type</b> | <b>Description</b>                 |
|-----------------------------|-------------|------------------------------------|
| <i>Text Value</i>           | <b>Text</b> | Text block to scan                 |
| <i>Truncated Text Value</i> | <b>Text</b> | Text block with first line removed |

The method ***STR\_Remove\_Line\_First*** will return a specified text block with the first line removed. Lines of text are considered to be delimited by carriage returns (ASCII value 13) within this method.

*Text Value* is the text block to scan.

*Truncated Text Value* is the text of *Text Value* with the first line removed. If there are no carriage returns with *Text Value* then *Truncated Text Value* will be empty.

**Note:** the method ***STR\_Remove\_Line\_First*** was added in BASH v1.5.1.



## **STR\_Remove\_NonAlphaNumeric**

***STR\_Remove\_NonAlphaNumeric***(*Text Value*) => *Filtered Text Value*

***STR\_Remove\_NonAlphaNumeric***

```
(  
    -> Text Value: Text  
)  
=> Filtered Text Value: Text
```

| Parameter                  | Type | Description          |
|----------------------------|------|----------------------|
| <i>Text Value</i>          | Text | Text value to filter |
| <i>Filtered Text Value</i> | Text | Filtered text value  |

The method ***STR\_Remove\_NonAlphaNumeric*** will removed all nonalphanumeric bytes from a text block.

Valid alphanumeric values include: lowercase letters, uppercase letters, and numbers.

*Text Value* is the supplied text value to be filtered.

*Filtered Text Value* is *Text Value* with all invalid bytes removed.

**Note:** the method ***STR\_Remove\_NonAlphaNumeric*** was added in BASH v1.5.1.



## STR\_Remove\_Spaces\_Post

**STR\_Remove\_Spaces\_Post**( *Text Value*) => *Trimmed Text Value*

**STR\_Remove\_Spaces\_Post**

```
(  
    -> Text Value: Text  
)  
=> Trimmed Text Value: Text
```

| Parameter                 | Type | Description        |
|---------------------------|------|--------------------|
| <i>Text Value</i>         | Text | Text value to trim |
| <i>Trimmed Text Value</i> | Text | Trimmed text value |

The method **STR\_Remove\_Spaces\_Post** will removed all trailing spaces (ASCII 32) from a text block.

*Text Value* is the supplied text value to be trimmed.

*Trimmed Text Value* is *Text Value* with all trailing spaces removed.

**Note:** the method **STR\_Remove\_Spaces\_Post** was added in BASH v1.5.1.



## STR\_Remove\_Spaces\_Pre

**STR\_Remove\_Spaces\_Pro**( *Text Value*) => *Trimmed Text Value*

**STR\_Remove\_Spaces\_Pro**

```
(  
    -> Text Value: Text  
)  
=> Trimmed Text Value: Text
```

| Parameter                 | Type | Description        |
|---------------------------|------|--------------------|
| <i>Text Value</i>         | Text | Text value to trim |
| <i>Trimmed Text Value</i> | Text | Trimmed text value |

The method *STR\_Remove\_Spaces\_Pre* will removed all leading spaces (ASCII 32) from a text block.

*Text Value* is the supplied text value to be trimmed.

*Trimmed Text Value* is *Text Value* with all leading spaces removed.

**Note:** the method *STR\_Remove\_Spaces\_Pre* was added in BASH v1.5.1.



## **STR\_Remove\_Spaces\_PrePost**

*STR\_Remove\_Spaces\_PrePost*( *Text Value*) => *Trimmed Text Value*

*STR\_Remove\_Spaces\_PrePost*

```
(  
    -> Text Value: Text  
)  
=> Trimmed Text Value: Text
```

| <b>Parameter</b>          | <b>Type</b> | <b>Description</b> |
|---------------------------|-------------|--------------------|
| <i>Text Value</i>         | <b>Text</b> | Text value to trim |
| <i>Trimmed Text Value</i> | <b>Text</b> | Trimmed text value |

The method *STR\_Remove\_Spaces\_PrePost* will removed all leading and trailing spaces (ASCII 32) from a text block.

*Text Value* is the supplied text value to be trimmed.

*Trimmed Text Value* is *Text Value* with all leading and trailing spaces removed.

**Note:** the method *STR\_Remove\_Spaces\_PrePost* was added in BASH v1.5.1.



## **STR\_Replace\_ASCII\_All**

**STR\_Replace\_ASCII\_All**( *Text Value*; *Old ASCII Value*; *New ASCII Value*)  
=> *New Text Value*

**STR\_Replace\_ASCII\_All**  
(  
-> *Text Value*: **Text**  
-> *Old ASCII Value*: **Longint**  
-> *New ASCII Value*: **Longint**  
)  
=> *New Text Value*: **Text**

| Parameter              | Type           | Description                           |
|------------------------|----------------|---------------------------------------|
| <i>Text Value</i>      | <b>Text</b>    | Text value to scan                    |
| <i>Old ASCII Value</i> | <b>Longint</b> | ASCII value to be replaced            |
| <i>New ASCII Value</i> | <b>Longint</b> | ASCII value to replace with           |
| <i>New Text Value</i>  | <b>Text</b>    | Text value with replacement completed |

The method **STR\_Replace\_ASCII\_All** will replace all occurrences of a specified ASCII value within a specified text block.

*Text Value* is the supplied text value to be scanned.

*Old ASCII Value* is the ASCII value within *Text Value* which is to be replaced.

*New ASCII Value* is the ASCII value within *Text Value* which will replace all occurrences of *Old ASCII Value*.

*New Text Value* is *Text Value* with all occurrences of *Old ASCII Value* replaced with *New ASCII Value*.

**Note:** the method **STR\_Replace\_ASCII\_All** was added in BASH v1.5.1.

---

## **STR\_Wrap\_in\_DoubleQuotes**

**STR\_Wrap\_in\_DoubelQuotes**( *Text Value*) => *Wrapped Text Value*

**STR\_Wrap\_in\_DoubelQuotes**  
(  
-> *Text Value*: **Text**

)  
=> *Wrapped Text Value*: Text

| Parameter                 | Type | Description                                |
|---------------------------|------|--|
| <i>Text Value</i>         | Text | Text block to wrap                         |
| <i>Wrapped Text Value</i> | Text | <i>Text Value</i> wrapped in double quotes |

The method *STR\_Wrap\_in\_DoubleQuotes* will wrap any text value with double quotes.

*Text Value* is the text block to wrap in double quotes.

*Wrapped Text Value* is *Text Value* wrapped in double quotes.

**Note:** the method *STR\_Wrap\_in\_DoubleQuotes* was added in BASH v1.5.1.

# TIME Module

The TIME module comprises basic routines for dealing with time variables in 4th Dimension. The routines are fairly simplistic in this release of the BASH component. But, similar to the SEM module, additional functionality will be added to the TIME module in future releases and it is strongly suggested that these routines be used in place of traditional native implementations.

**Note:** the TIME module was initially added in BASH v1.4.7.



## TIME\_Add\_Normalize

*TIME\_Add\_Normalize(First Time Addend; Second Time Addend) =>  
Normalized Time Sum*

*TIME\_Add\_Normalize  
(  
-> First Time Addend: Time  
-> Second Time Addend: Time  
)  
=> Normalized Time Sum: Time*

| Parameter                  | Type | Description   |
|----------------------------|------|---|
| <i>First Time Addend</i>   | Time | Time value to add   |
| <i>Second Time Addend</i>  | Time | Time value to add   |
| <i>Normalized Time Sum</i> | Time | Sum of two supplied time values, normalized to be a valid time value within a 24 hour day |

The method *TIME\_Add\_Normalize* returns the sum of two time supplied time values. The returned sum is in the format of a time value which has been normalized to be a valid time value.

*First Time Addend* and *Second Time Addend* are both supplied time values which are to be added together.



*Normalized Time Sum* is the sum of *First Time Addend* and *Second Time Addend*. *Normalized Time Sum* is normalized into a time value such; if the sum of *First Time Addend* and *Second Time Addend* would create a time value which is above the 24th hour, then 24 hours is removed from the sum to create a valid, normalized time value in *Normalized Time Sum*.

To determine whether *Normalized Time Sum* was normalized in the method *TIME\_Add\_Normalize*, call the method *TIME\_Get\_Sum\_Offset* afterwards.

### Example:

The following fragment of code exemplifies the use of the *TIME\_Add\_Normalize* and *TIME\_Get\_Sum\_Offset* methods. This fragment of code will add two time values together properly and determine whether a corresponding date value should be incremented to indicate that the sum of the two time values rolled over past midnight.

```
tTimeSum:= TIME_Add_Normalize (tTime1; tTime2)
If ( TIME_Get_Sum_Offset (tTime1; tTime2; tTimeSum)=1)
    `sum rolled over past midnight
Else
    `sum did not roll over past midnight
End if
```

**Note:** the method *TIME\_Add\_Normalize* was added in BASH v1.4.7.



## TIME\_Get\_Hours

*TIME\_Get\_Hours*(Time Value) => Number of Hours

```
TIME_Get_Hours
(
    -> Time Value: Time
)
=> Number of Hours: Longint
```

| Parameter              | Type    | Description  |
|------------------------|---------|--|
| <i>Time Value</i>      | Time    | Supplied time value                                      |
| <i>Number of Hours</i> | Longint | Number of hours in supplied time value <i>Time Value</i> |

The method ***TIME\_Get\_Hours*** returns the number of whole hours in a supplied time value.

*Time Value* is any given time value to extract the number of hours from.

*Number of Hours* is the number of whole hours within the supplied time value *Time Value*. No concessions are made to make *Number of Hours* correspond to a standard twelve (12) hour clock. Rather, the *Number of Hours* is merely a mathematical calculation performed on *Time Value*.

**Note:** the method ***TIME\_Get\_Hours*** was added in BASH v1.4.7.



## TIME\_Get\_Minutes

***TIME\_Get\_Minutes*** (*Time Value*) => *Number of Minutes*

```
TIME_Get_Minutes
(
    -> Time Value: Time
)
=> Number of Minutes: Longint
```

| Parameter                | Type    | Description  |
|--------------------------|---------|--|
| <i>Time Value</i>        | Time    | Supplied time value  |
| <i>Number of Minutes</i> | Longint | Number of minutes past hour in supplied time value <i>Time Value</i> |

The method ***TIME\_Get\_Minutes*** returns the number of whole minutes past the last whole hour in a supplied time value.

*Time Value* is any given time value to extract the number of minutes past the last whole hour from.

*Number of Minutes* is the number of whole minutes past the last whole hour within the supplied time value *Time Value*. The *Number of Minutes* is merely retrieved from a mathematical calculation on the supplied time value *Time Value*.

**Note:** the method *TIME\_Get\_Minutes* was added in BASH v1.4.7.

---

## **TIME\_Get\_Seconds**

*TIME\_Get\_Seconds* ( *Time Value*) => *Number of Seconds*

```
TIME_Get_Seconds
(
    -> Time Value: Time
)
=> Number of Seconds: Longint
```

| <b>Parameter</b>         | <b>Type</b>    | <b>Description</b>   |
|--------------------------|----------------|--|
| <i>Time Value</i>        | <b>Time</b>    | Supplied time value  |
| <i>Number of Seconds</i> | <b>Longint</b> | Number of seconds past minute in supplied time value <i>Time Value</i> |

The method *TIME\_Get\_Seconds* returns the number of whole seconds past the last whole minute in a supplied time value.

*Time Value* is any given time value to extract the number of seconds past the last whole minute from.

*Number of Seconds* is the number of whole seconds past the last whole minute within the supplied time value *Time Value*. The *Number of Seconds* is merely retrieved from a mathematical calculation on the supplied time value *Time Value*.

**Note:** the method *TIME\_Get\_Seconds* was added in BASH v1.4.7.



## TIME\_Get\_Sum\_Offset

*TIME\_Get\_Sum\_Offset*(Primary Time Value; Secondary Time Value; Tertiary Time Value) => Sum Cycle Status

*TIME\_Get\_Sum\_Offset*  
(  
    -> Primary Time Value: Time  
    -> Secondary Time Value: Time  
    -> Tertiary Time Value: Time  
)  
=> Sum Cycle Status: Longint

| Parameter            | Type    | Description  |
|----------------------|---------|--|
| Primary Time Value   | Time    | First time value to check against  |
| Secondary Time Value | Time    | Second time value to check against   |
| Tertiary Time Value  | Time    | Third time value to check against  |
| Sum Cycle Status     | Longint | Indicator for whether Tertiary Time Value is less than either Primary Time Value or Secondary Time Value |

The method *TIME\_Get\_Sum\_Offset* returns an indicator in for whether a particular time value is less than two other time values.

The *Primary Time Value* and *Secondary Time Value* must both be greater than *Tertiary Time Value* for *Sum Cycle Status* to be set to one (1). Otherwise, *Sum Cycle Status* will be set to zero (0).

The method *TIME\_Get\_Sum\_Offset* is meant to be used in conjunction with the method *TIME\_Add\_Normalize* to properly add two time values together and determine whether a day rollover occurred as a result of the summing.

**Example:**

The following fragment of code exemplifies the use of the *TIME\_Add\_Normalize* and *TIME\_Get\_Sum\_Offset* methods. This fragment of code will add two time values together properly and determine whether a corresponding date value should be incremented to indicate that the sum of the two time values rolled over past midnight.

```
tTimeSum:= TIME_Add_Normalize (tTime1; tTime2)
If ( TIME_Get_Sum_Offset (tTime1; tTime2; tTimeSum)=1)
    `sum rolled over past midnight
Else
    `sum did not roll over past midnight
End if
```

**Note:** the method *TIME\_Get\_Sum\_Offset* was added in BASH v1.4.7.

# TYPE Module

The TYPE module comprises basic routines for checking and confirming data types of different objects. The routines are fairly simplistic in this release of the BASH component. But, similar to the SEM module, additional functionality will be added to the TYPE module in future releases and it is strongly suggested that these routines be used in place of traditional native implementations.

## Unary and Array Classifications

It is worth knowing, also, that variable types in 4th Dimension have two different classifications: unary and array. Unary variables are capable of storing a single data value. Array variables are capable of storing zero, one, or more data values.

A complete listing of the unary variable types and their equivalent array data types follows:

| <u>Unary</u> | <u>Array</u> |
|--------------|--------------|
| BLOB         | n/a          |
| Boolean      | Boolean      |
| Date         | Date         |
| Graph        | n/a          |
| Integer      | Integer      |
| Longint      | Longint      |
| Picture      | Picture      |
| Pointer      | Pointer      |
| Real         | Real         |
| String       | String       |
| Text         | Text         |
| Time         | Longint      |



## **TYPE\_Compare\_Dereferenced\_Type**

**TYPE\_Compare\_Dereferenced\_Type** ( *Referenced Variable; Variable Type*) =>  
*Match State*

**TYPE\_Compare\_Dereferenced\_Type**

```
(
    -> Referenced Variable: Pointer
    -> Variable Type: Longint
)
=> Match State: Longint
```

| <b>Parameter</b>           | <b>Type</b>    | <b>Description</b>  |
|----------------------------|----------------|---|
| <i>Referenced Variable</i> | <b>Pointer</b> | Reference to a variable which will have its type checked  |
| <i>Variable Type</i>       | <b>Longint</b> | Variable type to compare to (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |
| <i>Match State</i>         | <b>Longint</b> | State of type match check   |

The method *TYPE\_Compare\_Dereferenced\_Type* will compare a referenced variable type with a supplied variable type. It will return an indicator for whether the types match or an error condition.

The *Referenced Variable* parameter is a pointer to any variable whose type is going to be checked.

The *Variable Type* parameter is a variable type value to check against the *Referenced Variable* parameter. The list of valid type values are available as native constants in 4th Dimension under the *Field and Variable Types* grouping.

The *Match State* return parameter is the indicator for the match validity of the *Referenced Variable* parameter and the *Variable Type* parameter. Valid values for the *Match State* return parameter are as follows:

| <u>Value</u> | <u>Meaning</u>                              |
|--------------|---|
| 1            | Types match                                 |
| 0            | Types do not match                          |
| - 1          | <i>Referenced Variable</i> is Nil           |
| - 2          | <i>Referenced Variable</i> is not a pointer |



## **TYPE\_Get\_Array\_by\_Unary**

**TYPE\_Get\_Array\_by\_Unary** ( *Unary Type* ) => *Array Type*

## **TYPE\_Get\_Array\_by\_Unary**

```
(  
    -> Unary Type: Longint  
)  
=> Array Type: Longint
```

| Parameter  | Type    | Description  |
|------------|---------|--|
| Unary Type | Longint | Unary data type (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> )            |
| Array Type | Longint | Equivalent array data type (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |

The method **TYPE\_Get\_Array\_by\_Unary** will return the array equivalent data type for any specified unary data type. Variable data type values are designated by the 4D constants *Field* and *Variable Types*.

*Unary Type* is any unary variable type. Array variable types can be specified within *Unary Type* for convenience.

*Array Type* is the equivalent array data type for a value passed in *Unary Type*. If *Unary Type* is invalid, *Array Type* will be set to -1. If *Unary Type* has no equivalent array variable type, *Array Type* will be set to -2.

**Note:** the method **TYPE\_Get\_Array\_by\_Unary** was added in BASH v1.5.1.



## **TYPE\_Get\_Unary\_by\_Array**

**TYPE\_Get\_Unary\_by\_Array** (Array Type) => Unary Type

```
TYPE_Get_Unary_by_Array  
(  
    -> Array Type: Longint  
)  
=> Unary Type: Longint
```

| Parameter | Type | Description |
|-----------|------|-------------|
|-----------|------|-------------|



|            |         |  |
|------------|---------|--|
| Array Type | Longint | Array data type (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> )            |
| Unary Type | Longint | Equivalent array data type (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |

The method ***TYPE\_Get\_Unary\_by\_Array*** will return the unary equivalent data type for any specified array data type. Variable data type values are designated by the 4D constants *Field* and *Variable Types*.

*Array Type* is any array variable type. Unary variable types can be specified within *Array Type* for convenience.

*Unary Type* is the equivalent unary data type for a value passed in *Array Type*. If *Array Type* is invalid, *Unary Type* will be set to -1.

**Note:** the method ***TYPE\_Get\_Unary\_by\_Array*** was added in BASH v1.5.1.



## **TYPE\_qi\_Array**

***TYPE\_qi\_Array*** ( Variable Type) => Array Match State

***TYPE\_qi\_Array***  
 (  
     -> Variable Type: Longint  
 )  
     => Array Match State: Longint

| Parameter         | Type    | Description  |
|-------------------|---------|--|
| Variable Type     | Longint | Variable type to check (variable types are designated by the 4D constants <i>Field</i> and <i>Variable Types</i> ) |
| Array Match State | Longint | State of type match check  |

The method ***TYPE\_qi\_Array*** will check whether a supplied variable type is any form of array variable.

The *Variable Type* parameter is any variable type value which is consistent with the native 4th Dimension variable type values found in the *Field and Variable Types* constants grouping. This variable type will be checked for whether it is some form of array, regardless of the exact type of array.

The returned *Array Match State* parameter is an indicator of whether the *Variable Type* value is an array type. If *Array Match State* is zero (0) then the supplied *Variable Type* is not an array. If *Array Match State* is one (1) then the supplied *Variable Type* is an array of some type.



## **TYPE\_qi\_BLOB**

**TYPE\_qi\_BLOB** ( *Variable Type* ) => *BLOB Match State*

**TYPE\_qi\_BLOB**

```
(
    -> Variable Type: Longint
)
=> BLOB Match State: Longint
```

| Parameter               | Type    | Description   |
|-------------------------|---------|---|
| <i>Variable Type</i>    | Longint | Variable type to check (variable types are designated by the 4D constants <i>Field and Variable Types</i> ) |
| <i>BLOB Match State</i> | Longint | State of type match check   |

The method **TYPE\_qi\_BLOB** will check whether a supplied variable type is a BLOB.

The *Variable Type* parameter is any variable type value which is consistent with the native 4th Dimension variable type values found in the *Field and Variable Types* constants grouping. This variable type will be checked for whether it is of type BLOB.

The returned *BLOB Match State* parameter is an indicator of whether the *Variable Type* value is BLOB type. If *BLOB Match State* is zero (0) then the supplied *Variable*

*Type* is not a BLOB. If *BLOB Match State* is one (1) then the supplied *Variable Type* is a BLOB.

# URL Module

The URL module comprises basic routines for handling and manipulating fully formatted, RFC compliant URLs. The routines within the URL module allow for the creation and parsing of properly formatted URLs. The current version of the URL module supports nine (9) different URL schemes. As needed, more URL schemes will be supported in future releases of the BASH component.

## Fully Formatted URLs

RFC compliant URL formatting is discussed in RFC 1738. You can get a copy of this RFC from:

[http://www.deepskytech.com/rfcs/rfc\\_1738.txt](http://www.deepskytech.com/rfcs/rfc_1738.txt)

The basic format for URLs is as follows:

```
<scheme><username>:<password>@<host>:<port>/<path>  
$<directarg>?<searchargs>
```

The rules for which values are allowed for a particular scheme are available within RFC 1738. As well, the rules for the inclusion of different separator values are dependant upon the inclusion of other variable values within a particular URL scheme.

<scheme> is often known as the protocol. It is an indicator, often ending with a colon (":") or a colon followed by two slashes ("://"). Common values for schemes include "http://", "ftp://", and "mailto:". The URL scheme constants provided within the BASH module provide a means to indicate different scheme values more compactly and efficiently. Routines within the URL module provide a means for translating back and forth between the textual value of a scheme and its constant value.

The other values that comprise an URL can be learned about by reading RFC 1738, referenced above.

Note: the URL module was initially added in BASH v1.5.7.



## URL\_Extract\_DirectParam

**URL\_Extract\_DirectParam** ( *Fully Formatted URL* ) => *Direct Parameter*

**URL\_Extract\_DirectParam**

```
(  
    -> Fully Formatted URL : Text  
)  
=> Direct Parameter : Text
```

| Parameter                  | Type | Description   |
|----------------------------|------|---|
| <i>Fully Formatted URL</i> | Text | Fully formatted, RFC compliant URL to extract discrete value from |
| <i>Direct Parameter</i>    | Text | Direct parameter value extracted from <i>Fully Formatted URL</i>  |

The method **URL\_Extract\_DirectParam** will return the direct parameter value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Direct Parameter* is the direct parameter value, if any, extracted from the specified *Fully Formatted URL* .

Note: the method **URL\_Extract\_DirectParam** was added in BASH v1.5.7.



## URL\_Extract\_Host

**URL\_Extract\_Host** ( *Fully Formatted URL* ) => *Host*

**URL\_Extract\_Host**

```
(
    -> Fully Formatted URL : Text
)
=> Host : Text
```

| Parameter                  | Type | Description   |
|----------------------------|------|---|
| <i>Fully Formatted URL</i> | Text | Fully formatted, RFC compliant URL to extract discrete value from |
| <i>Host</i>                | Text | Host name value extracted from <i>Fully Formatted URL</i>         |

The method ***URL\_Extract\_Host*** will return the host name value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Host* is the host name value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method ***URL\_Extract\_Host*** was added in BASH v1.5.7.

---

## **URL\_Extract\_Password**

***URL\_Extract\_Password*** ( *Fully Formatted URL* ) => *Password*

```
URL_Extract_Password
(
    -> Fully Formatted URL : Text
)
=> Password: Text
```

| Parameter                  | Type | Description   |
|----------------------------|------|---|
| <i>Fully Formatted URL</i> | Text | Fully formatted, RFC compliant URL to extract discrete value from |
| <i>Password</i>            | Text | Password value extracted from <i>Fully Formatted URL</i>          |

The method ***URL\_Extract\_Password*** will return the password value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Password* is the password value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method *URL\_Extract\_Password* was added in BASH v1.5.7.



## **URL\_Extract\_Path**

**URL\_Extract\_Path** ( *Fully Formatted URL* ) => *Path*

**URL\_Extract\_Path**

```
(  
    -> Fully Formatted URL : Text  
)  
=> Path: Text
```

| Parameter                  | Type | Description   |
|----------------------------|------|---|
| <i>Fully Formatted URL</i> | Text | Fully formatted, RFC compliant URL to extract discrete value from |
| <i>Path</i>                | Text | Path value extracted from <i>Fully Formatted URL</i>              |

The method *URL\_Extract\_Path* will return the path value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Path* is the path value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method *URL\_Extract\_Path* was added in BASH v1.5.7.



## **URL\_Extract\_Path\_w\_Params**

**URL\_Extract\_Path\_w\_Params** ( *Fully Formatted URL* ) => *Path with Parameters*

## **URL\_Extract\_Path\_w\_Params**

```
(  
    -> Fully Formatted URL : Text  
)  
=> Path with Parameters : Text
```

| <b>Parameter</b>            | <b>Type</b> | <b>Description</b>  |
|-----------------------------|-------------|---|
| <i>Fully Formatted URL</i>  | Text        | Fully formatted, RFC compliant URL to extract discrete value from                               |
| <i>Path with Parameters</i> | Text        | Path value with attached direct and search parameters extracted from <i>Fully Formatted URL</i> |

The method **URL\_Extract\_Path\_w\_Params** will return the path value, direct parameter, and search parameters extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Path with Parameters* is the path value with the subsequent direct parameter and search arguments, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method **URL\_Extract\_Path\_w\_Params** was added in BASH v1.5.7.



## **URL\_Extract\_Port**

**URL\_Extract\_Port** ( *Fully Formatted URL* ) => *Port*

```
URL_Extract_Port  
(  
    -> Fully Formatted URL : Text  
)  
=> Port : Longint
```

| <b>Parameter</b>           | <b>Type</b> | <b>Description</b>  |
|----------------------------|-------------|---|
| <i>Fully Formatted URL</i> | Text        | Fully formatted, RFC compliant URL to extract discrete value from |
| <i>Port</i>                | Longint     | Port value extracted from <i>Fully Formatted URL</i>              |



The method ***URL\_Extract\_Port*** will return the port value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Port* is the port value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method ***URL\_Extract\_Port*** was added in BASH v1.5.7.



## **URL\_Extract\_Scheme\_i**

***URL\_Extract\_Scheme\_i*** ( *Fully Formatted URL* ) => *Scheme Constant*

***URL\_Extract\_Scheme\_i***  
(  
    -> *Fully Formatted URL* : **Text**  
)  
=> *Scheme Constant* : **Longint**

| <b>Parameter</b>           | <b>Type</b>    | <b>Description</b>   |
|----------------------------|----------------|--|
| <i>Fully Formatted URL</i> | <b>Text</b>    | Fully formatted, RFC compliant URL to extract discrete value from          |
| <i>Scheme Constant</i>     | <b>Longint</b> | Scheme constant value for scheme extracted from <i>Fully Formatted URL</i> |

The method ***URL\_Extract\_Scheme\_i*** will return the scheme constant value for the scheme extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Scheme Constant* is the scheme constant value for the scheme value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method ***URL\_Extract\_Scheme\_i*** was added in BASH v1.5.7.



## URL\_Extract\_Scheme\_x

**URL\_Extract\_Scheme\_x** ( *Fully Formatted URL* ) => *Scheme*

**URL\_Extract\_Scheme\_x**

```
(  
    -> Fully Formatted URL :Text  
)  
=> Scheme :Text
```

| Parameter                  | Type | Description   |
|----------------------------|------|---|
| <i>Fully Formatted URL</i> | Text | Fully formatted, RFC compliant URL to extract discrete value from |
| <i>Scheme</i>              | Text | Textual scheme value extracted from <i>Fully Formatted URL</i>    |

The method **URL\_Extract\_Scheme\_x** will return the textual scheme value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Scheme* is the textual scheme value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method **URL\_Extract\_Scheme\_x** was added in BASH v1.5.7.



## URL\_Extract\_SearchParams

**URL\_Extract\_SearchParams** ( *Fully Formatted URL* ) => *Search Parameters*

**URL\_Extract\_SearchParams**

```
(  
    -> Fully Formatted URL :Text  
)  
=> Search Parameters :Text
```

| Parameter | Type | Description |
|-----------|------|-------------|
|-----------|------|-------------|

|                            |             |  |
|----------------------------|-------------|--|
| <i>Fully Formatted URL</i> | <b>Text</b> | <b>Fully formatted, RFC compliant URL to extract discrete value from</b> |
| <i>Search Parameters</i>   | <b>Text</b> | <b>Search parameters value extracted from <i>Fully Formatted URL</i></b> |

The method ***URL\_Extract\_SearchParams*** will return the search parameters value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Search Parameters* is the search parameters value, if any, extracted from the specified *Fully Formatted URL* .

**Note:** the method ***URL\_Extract\_SearchParams*** was added in BASH v1.5.7.



## **URL\_Extract\_Username**

***URL\_Extract\_Username*** ( *Fully Formatted URL* ) => *Username*

***URL\_Extract\_Username***  
 (  
     -> *Fully Formatted URL* : **Text**  
 )  
     => *Username* : **Text**

| <b>Parameter</b>           | <b>Type</b> | <b>Description</b>   |
|----------------------------|-------------|--|
| <i>Fully Formatted URL</i> | <b>Text</b> | <b>Fully formatted, RFC compliant URL to extract discrete value from</b> |
| <i>Username</i>            | <b>Text</b> | <b>User name value extracted from <i>Fully Formatted URL</i></b>         |

The method ***URL\_Extract\_Username*** will return the user name value extracted from a fully formatted URL.

*Fully Formatted URL* is a full, RFC compliant URL which is to have data extracted from it.

*Username* is the user name value, if any, extracted from the specified *Fully Formatted URL* .

Note: the method *URL\_Extract\_Username* was added in BASH v1.5.7.

---

## **URL\_Get\_Scheme\_i**

**URL\_Get\_Scheme\_i** (*Scheme* ) => *Scheme Constant*

**URL\_Get\_Scheme\_i**  
(  
    -> *Scheme* : **Text**  
)  
    => *Scheme Constant* : **Longint**

| Parameter              | Type           | Description  |
|------------------------|----------------|--|
| <i>Scheme</i>          | <b>Text</b>    | Textual scheme value   |
| <i>Scheme Constant</i> | <b>Longint</b> | Scheme constant value matching supplied textual scheme value |

The method *URL\_Get\_Scheme\_i* will return scheme constant value for a specified textual scheme value.

*Scheme* is the textual scheme value to get the scheme constant for.

*Scheme Constant* is the scheme constant value matching the supplied textual scheme value, *Scheme* . *Scheme Constant* will be set to zero (0) if the *Scheme* is not a valid scheme.

Note: the method *URL\_Get\_Scheme\_i* was added in BASH v1.5.7.

---

## **URL\_Get\_Scheme\_x**

**URL\_Get\_Scheme\_x** (*Scheme Constant* ) => *Scheme*

**URL\_Get\_Scheme\_x**  
(  
    -> *Scheme Constant* : **Longint**  
)

=> *Scheme* : **Text**

| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>   |
|------------------------|----------------|--|
| <i>Scheme Constant</i> | <b>Longint</b> | Scheme constant value  |
| <i>Scheme</i>          | <b>Text</b>    | Textual scheme value matching supplied scheme constant value |

The method *URL\_Get\_Scheme\_x* will return textual scheme value for a specified scheme constant value.

*Scheme Constant* is the scheme constant value to get the textual scheme value for.

*Scheme* is the textual scheme value matching the supplied scheme constant value, *Scheme Constant*. *Scheme* will be set to NULL (empty) if the *Scheme Constant* is not a valid scheme constant value.

**Note:** the method *URL\_Get\_Scheme\_x* was added in BASH v1.5.7.



## **URL\_Make\_URL**

**URL\_Make\_URL** (*Scheme* ; *Username* ; *Password* ; *UnPw Flags* ; *Host* ; *Port* ; *Path* ; *Direct Parameter* ; *Referenced Search Arguments Names* ; *Referenced Search Arguments Values* ) => *URL*

### **URL\_Make\_URL**

```
(  
    -> Scheme : Longint  
    -> Username : Text  
    -> Password : Text  
    -> UnPw Flags : Longint  
    -> Host : Text  
    -> Port : Longint  
    -> Path : Text  
    -> Direct Parameter : Text  
    -> Referenced Search Arguments Names : Pointer  
    -> Referenced Search Arguments Values : Pointer  
)  
=> URL : Text
```

| <b>Parameter</b> | <b>Type</b> | <b>Description</b> |
|------------------|-------------|--------------------|
|------------------|-------------|--------------------|

|   |         |  |
|---|---------|--|
| <i>Scheme</i>                             | Longint | Scheme constant value for URL to be created                                    |
| <i>Username</i>                           | Text    | Username for URL to be created   |
| <i>Password</i>                           | Text    | Password for URL to be created   |
| <i>UnPw Flags</i>                         | Longint | Coded username and password flags for URL to be created                        |
| <i>Host</i>                               | Text    | Host name for URL to be created  |
| <i>Port</i>                               | Longint | Port for URL to be created   |
| <i>Path</i>                               | Text    | Path for URL to be created   |
| <i>Direct Parameter</i>                   | Text    | Direct Parameter for URL to be created   |
| <i>Referenced Search Arguments Names</i>  | Pointer | Pointer to text array containing search arguments names for URL to be created  |
| <i>Referenced Search Arguments Values</i> | Pointer | Pointer to text array containing search arguments values for URL to be created |
| <i>URL</i>                                | Text    | Fully formatted, RFC compliant URL   |

The method *URL\_Make\_URL* will a properly formatted, RFC compliant URL for the values specified. See RFC 1738, or the method comments in the 4D Explorer window in 4D, for details on which URL values are available with different URL schemes.

*Scheme* is the scheme constant value for the URL to be created. Valid scheme constant values are listed in the URL Schemes constants group included with the BASH component.

*Username* is the user name value, if any, for the URL to be created.

*Password* is the password value, if any, for the URL to be created.

*UnPw Flags* is a flags value to indicate whether a username and possibly password is to be forced for inclusion with an URL even if the individual values are empty. The following tables lists the valid values, and their meaning, for this parameter:

| <u>Value</u> | <u>Meaning</u>                           |
|--------------|--|
| 0            | do not force include either value        |
| 1            | force include password only              |
| 2            | force include both username and password |

*Host* is the host name value, if any, for the URL to be created.

*Port* is the port value, if any, for the URL to be created.

*Path* is the path value, if any, for the URL to be created. Note, the path value does **not** have a leading slash in most cases; a single slash in the URL is a delimiter and is not part of the *Path* value.

*Direct Parameter* is the direct parameter value, if any, for the URL to be created.

*Referenced Search Arguments Names* is a pointer to a text array containing search arguments names, if any, for the URL to be created. This value can be set to NULL to skip.

*Referenced Search Arguments Values* is a pointer to a text array containing search arguments values, if any, for the URL to be created. This value can be set to NULL to skip.

*URL* is the fully formatted, RFC compliant URL created from the specified values.

**Note:** the method *URL\_Make\_URL* was added in BASH v1.5.7.

# VAR Module

The VAR module comprises basic routines for handling and manipulating variables directly. The routines are fairly simplistic in this release of the BASH component. But, similar to the SEM and TYPE modules, additional functionality will be added to the VAR module in future releases and it is strongly suggested that these routines be used in place of traditional native implementations.



## VAR\_Get\_Variable\_Name

**VAR\_Get\_Variable\_Name** (*Referenced Variable*) => *Variable Name*

**VAR\_Get\_Variable\_Name**  
(  
    -> *Referenced Variable*: **Pointer**  
)  
    => *Variable Name*: **Text**

| Parameter                  | Type           | Description                               |
|----------------------------|----------------|---|
| <i>Referenced Variable</i> | <b>Pointer</b> | Referenced variable to get the name of    |
| <i>Variable Name</i>       | <b>Text</b>    | Actual name of <i>Referenced Variable</i> |

The method **VAR\_Get\_Variable\_Name** will return the actual variable name for any referenced variable supplied in the *Referenced Variable* parameter. This method is practically equivalent to the native 4th Dimension command **RESOLVE POINTER**.



## VAR\_qi\_Null\_Pointer

**VAR\_qi\_Null\_Pointer** (*Reference Value*) => *nil Match State*

**VAR\_qi\_Null\_Pointer**  
(  
    -> *Reference Value*: **Pointer**  
)  
    => *nil Match State*: **Longint**



| <b>Parameter</b>       | <b>Type</b>    | <b>Description</b>   |
|------------------------|----------------|--|
| <i>Reference Value</i> | <b>Pointer</b> | Any form of a referenced (pointer)                             |
| <i>nil Match State</i> | <b>Longint</b> | Indicator for whether <i>Reference Value</i> is a NULL pointer |

The method *VAR\_qi\_Null\_Pointer* will check the *Reference Value* parameter and return an indicator for whether it is a NULL pointer. This method is practically equivalent to the native 4th Dimension command **Nil**. If the *Reference Value* parameter is a NULL pointer, the returned value *nil Match State* will be set to one (1); if the *Reference Value* parameter is not a NULL pointer, the returned value *nil Match State* will be set to zero (0).

## WORD Module

The WORD module provides operations which can be performed on four byte word data types. These differ often from 4D native longint data types in the actual meanings of the encoded values.

For instance, one common type of four byte word value is the unsigned longint. Where a native 4D longint value has of values from  $-2^{31}$  to  $(2^{31}) - 1$ , an unsigned longint has a range of 0 to  $2^{32}$ .

Different words require that operation be performed upon them differently. The basic routines available in the WORD module provide a small basis for operating on words of different types. As well, basic bit operations have been included in the WORD module to increase the functionality which is not already included natively in 4D's native bit operations.

**Note:** the WORD module was added in BASH v1.5.4.



### WORD\_Add\_Unsigned

**WORD\_Add\_Unsigned** (*First Addend* ; *Second Addend* ) => *Word Sum*

**WORD\_Add\_Unsigned**

```
(  
    -> First Addend : Longint  
    -> Second Addend : Longint  
)  
=> Word Sum : Longint
```

| Parameter            | Type    | Description  |
|----------------------|---------|--|
| <i>First Addend</i>  | Longint | First addend for unsigned longint addition                           |
| <i>Second Addend</i> | Longint | Second addend for unsigned longint addition                          |
| <i>Word Sum</i>      | Longint | Unsigned longint sum of <i>First Addend</i> and <i>Second Addend</i> |

The method ***WORD\_Add\_Unsigned*** will perform an unsigned longint addition upon two supplied unsigned longint values. The unsigned longint sum will be returned.

*First Addend* and *Second Addend* are the two unsigned longint values which are to be added.

*Word Sum* is the unsigned longint sum of *First Addend* and *Second Addend*.

**Note:** the method ***WORD\_Add\_Unsigned*** was added in BASH v1.5.4.



## **WORD\_Clear\_Bits**

***WORD\_Clear\_Bits*** ( *Word* { ; *Bit to Clear* { ; ... } } ) => *Word Result*

***WORD\_Clear\_Bits***

```
(  
    -> Word : Longint  
    { -> Bit to Clear : Longint }  
)  
    -> Word Result : Longint
```

| Parameter           | Type    | Description                                |
|---------------------|---------|--|
| <i>Word</i>         | Longint | Word value to clear bits within            |
| <i>Bit to Clear</i> | Longint | Zero, one, or more bit numbers to clear    |
| <i>Word Result</i>  | Longint | Resulting word with specified bits cleared |

The method ***WORD\_Clear\_Bits*** will clear one or more numbered bits within a longint and return the resulting longint.

*Word* is the longint value to have one or more bits cleared within.

*Bit to Clear* is the bit number to clear within *Word*. Multiple bit numbers can be passed to this method. Valid bit numbers are between zero (0) and thirty-one (31).

*Word Result* is the longint value of *Word* with the specified bits cleared.

**Note:** the method *WORD\_Clear\_Bits* was added in BASH v1.5.5.



## **WORD\_Get\_Bit\_Range**

**WORD\_Get\_Bit\_Range** ( *Word* ; *Start Extract Bit Number* ; *End Extract Bit Number* ; *Start Result Bit Number* ) => *Word Result*

### **WORD\_Get\_Bit\_Range**

```
(  
    -> asd : Longint  
    -> Start Extract Bit Number : Longint  
    -> End Extract Bit Number : Longint  
    -> Start Result Bit Number : Longint  
)  
=> Word Result : Longint
```

| Parameter                       | Type    | Description  |
|---------------------------------|---------|--|
| <i>Word</i>                     | Longint | Word value to extract bit range from                               |
| <i>Start Extract Bit Number</i> | Longint | Bit number in supplied word to begin extraction from               |
| <i>End Extract Bit Number</i>   | Longint | Bit number in supplied word to end extraction from                 |
| <i>Start Result Bit Number</i>  | Longint | Bit number in resulting word to place extraction into              |
| <i>Word Result</i>              | Longint | Resulting word for extracted bit range place in specified location |

The method *WORD\_Get\_Bit\_Range* will extract a range of bit values from a supplied longint and return it in a particular location within a longint.

*Word* is the longint value to extract a bit range from.

*Start Extract Bit Number* is the starting bit number to extract from *Word* . Valid bit numbers are between zero (0) and thirty-one (31).

*End Extract Bit Number* is the end bit number to extract from *Word* . Valid bit numbers are between zero (0) and thirty-one (31).

*Start Result Bit Number* is the starting bit number within the result to place the extracted bits into. This allows for the result of the extracted bits to automatically be shifted in the result for the convenience of the developer. Valid bit numbers are between zero (0) and thirty-one (31).

*Word Result* is the longint value of the extracted bits located at the bit location within the value specified in the method call.

**Note:** the method *WORD\_Get\_Bit\_Range* was added in BASH v1.5.5.



## **WORD\_Rotate\_Left**

**WORD\_Rotate\_Left** ( *Word Value* ; *Left Shift Count* ) => *Rotated Word*

**WORD\_Rotate\_Left**

```
(  
    -> Word Value : Longint  
    -> Left Shift Count : Longint  
)  
=> Rotated Word: Longint
```

| Parameter               | Type    | Description   |
|-------------------------|---------|---|
| <i>Word Value</i>       | Longint | Word value to operate on                                  |
| <i>Left Shift Count</i> | Longint | Bit count to rotate left                                  |
| <i>Rotated Word</i>     | Longint | Resulting word value rotated left <i>Left Shift Count</i> |

The method *WORD\_Rotate\_Left* will do a left rotating bit shift on a specified word value for a specified number of bits.

Rotated bits from the left end of a word will be attached as new bits on the right end of the word, maintaining the 32 bit integrity of the word value.

*Word Value* is the four byte word value which is to be left shifted rotationally.

*Left Shift Count* is the number of bits *Word Value* will be rotationally shifted left.

*Rotated Word* is the resulting *Word Value* after it has been rotationally shifted left *Left Shift Count*.

**Note:** the method *WORD\_Rotate\_Left* was added in BASH v1.5.4.



## **WORD\_Set\_Bits**

**Word\_Set\_Bits** ( *Word* { ; *Bit to Set* { ; ... } } ) => *Word Result*

### **Word\_Set\_Bits**

```
(  
    -> Word : Longint  
    { -> Bit to Set : Longint }  
)  
    -> Word Result : Longint
```

| <b>Parameter</b>   | <b>Type</b> | <b>Description</b>                     |
|--------------------|-------------|--|
| <i>Word</i>        | Longint     | Word value to set bits within          |
| <i>Bit to Set</i>  | Longint     | Zero, one, or more bit numbers to set  |
| <i>Word Result</i> | Longint     | Resulting word with specified bits set |

The method *WORD\_Set\_Bits* will set one or more numbered bits within a longint and return the resulting longint.

*Word* is the longint value to have one or more bits set within.

*Bit to Set* is the bit number to set within *Word*. Multiple bit numbers can be passed to this method. Valid bit numbers are between zero (0) and thirty-one (31).

*Word Result* is the longint value of *Word* with the specified bits set.

**Note:** the method *WORD\_Set\_Bits* was added in BASH v1.5.5.





# Version History

The following is a brief version history of the BASH component. It details release notes, bug fixes, and changes for each version publicly available.

It is worth noting that the version jumps of the BASH component are intentional. The code within the BASH module is actually stored in a master 4th Dimension application within Deep Sky Technologies, Inc. As core code within DSTi changes, it is changed in this master application and the version is incremented at specific intervals. The BASH component is kept synchronous with the master structure for ease of maintenance of version numbers.

In general, version numbers should not be an issue within your usage of the BASH component. And, in any case, the full history of different versions of the BASH component are fully detailed in this section.

# BASh v1.5.9

*released 20010706*

## Changes:

Added methods to the ARR module:

ARR\_Find\_First\_Binary  
ARR\_Find\_Last\_Same

Added methods to the BLOB module:

BLOB\_Change\_Case  
BLOB\_XOR\_Bytes

Added methods to the CODEC module:

CODEC\_Decode\_UUEncode\_File  
CODEC\_Decode\_UUEncode\_x  
CODEC\_Decode\_UUEncode\_z  
CODEC\_Encode\_CRAMMD5\_z  
CODEC\_Encode\_KeyedMD5\_z  
CODEC\_Encode\_UUEncode\_File  
CODEC\_Encode\_UUEncode\_x  
CODEC\_Encode\_UUEncode\_z

Set all \_ERROR methods in all modules to contain a TRACE command to assist in debugging.

# BASh v1.5.8

*released 20010625*

## Changes:

Added method to the BLOB module:

BLOB\_Find\_Byte

Added methods to the CODEC module:

CODEC\_Decode\_Hex\_x

CODEC\_Decode\_Hex\_z

CODEC\_Encode\_Hex\_x

CODEC\_Encode\_Hex\_z

Added methods to the DATE module:

DATE\_Get\_ISO8601\_GMT

DATE\_Get\_Month\_f\_ShortName

Added method to the DTS module:

DTS\_Convert\_f\_RFC

Fixed a bug in the method ENV\_Get\_BASh\_RF\_FullPath in which erroneously the system's 4DX directory would be scanned for the Affix document even if the Affix document was already found next to the application in the 4DX directory.

# BASh v1.5.7

*released 20010604*

## Changes:

Added the PTEXT module to the BASh component. Added methods to the PTEXT module:

- PTEXT\_Set\_Values\_ax
- PTEXT\_Set\_Values\_az
- PTEXT\_Set\_Values\_x
- PTEXT\_Set\_Values\_z

Added the URL module to the BASh component. Added methods to the URL module:

- URL\_Extract\_DirectParam
- URL\_Extract\_Host
- URL\_Extract\_Password
- URL\_Extract\_Path
- URL\_Extract\_Path\_w\_Params
- URL\_Extract\_Port
- URL\_Extract\_Scheme\_i
- URL\_Extract\_Scheme\_x
- URL\_Extract\_SearchParams
- URL\_Extract\_Username
- URL\_Get\_Scheme\_i
- URL\_Get\_Scheme\_x
- URL\_Make\_URL

Add URL schemes constants to the Affix document for use in the URL module.

Added URL scheme 'STR#' resource to the Affix document for use in translating URL schemes from constants to their textual equivalents.

Added method to the BLOB module:

- BLOB\_Find\_Text\_Case
- BLOB\_Replace\_Text\_Case
- BLOB\_Replace\_Text\_NonCase

Added method to the STR module:

STR\_Position\_NonAlpha  
STR\_Position\_NonAlphaNumeric  
STR\_Position\_NonNumeric

## BASh v1.5.6

*released 20010516*

### Changes:

Added method to the RES module:

RES\_Get\_Fork\_Size

Fixed a bug in the initialization code for the component wherein the searching for the Affix BASh document could fail if there was a document in the 4DX folder that did not have a resource fork.

Fixed a bug in the method *CRYPT\_Get\_TEA\_Keys\_f\_Text* in which some of the variable initialization was performed incorrectly (thanks JM).

# BASh v1.5.5

*released 20010425*

## Changes:

Added methods to the ARR module:

ARR\_Coerce\_to\_Text  
ARR\_Coerce\_from\_Text

Added method to the BLOB module:

BLOB\_Replace\_Byte

Added methods to the CODEC module:

CODEC\_Decode\_URL\_z  
CODEC\_Encode\_URL\_z

Added the CRYPT module to the BASh component. Added methods to the CRYPT module:

CRYPT\_Decrypt\_TEA\_x  
CRYPT\_Decrypt\_TEA\_z  
CRYPT\_Encrypt\_TEA\_x  
CRYPT\_Encrypt\_TEA\_z  
CRYPT\_Get\_TEA\_Keys\_f\_Text

Added methods to the RES module:

RES\_Load\_HTbl  
RES\_Parse\_HTbl\_Cells  
RES\_Parse\_HTbl\_Rows  
RES\_Parse\_HTbl\_Table  
RES\_Set\_HTbl\_Resource

Added the SERNO module to the BASh component. Added methods to the SERNO module:

SERNO\_Create\_SerialNumber  
SERNO\_Decode\_SerialNumber  
SERNO\_Get\_Beta

SERNO\_Get\_MajorVersion  
SERNO\_Get\_MinorVersion  
SERNO\_Get\_Month  
SERNO\_Get\_ProductCode  
SERNO\_Get\_Users  
SERNO\_Get\_Year

Added methods to the WORD module:

WORD\_Clear\_Bits  
WORD\_Get\_Bit\_Range  
WORD\_Set\_Bits

Upgraded 4D Pack from v6.7.0 to v6.7.1.

For future compatibility and avoidance of particular bugs under Windows, the Affix documents on Windows have been renamed to no longer begin with "Affix\_" and instead begin with "afx\_".

Fixed a bug in *DTS\_Get\_Current* in which, under rare circumstances, the date could be one date and the time from the following day. 4D needs to provide a way to atomically get both the current date and the current time. [Thanks to TK of IRGi for the bug report and bug fix.]

Fixed a crashing bug when compiled under Windows in which calls to some methods with a referenced pointer array would fail. This is the old 4D bug involving assigning a referenced NULL pointer to a referenced pointer variable value (4D SA has still not fixed this bug since 4D v3.5.x). The bug fix is to just not make the assignment when compiled under Windows in the offending methods.

Fixed bugs within the *CONV\_IP\_to\_Longint* and *CONV\_Longint\_to\_IP* methods in which the values which would convert to negative 4D longint values were being handled incorrectly.

Fixed a bug in applying the padding to the encoding object within the method *CODEC\_Encode\_MD5\_z*.



Fixed a bug in the method

*ENV\_Get\_Application\_Name\_Short* in which the resource fork of the structure was not being opened or referenced correctly.

Increased DSS variable space from 100 to 200 objects each for text, longint, BLOB, text array, and longint array. Remaining data types were left at 100 objects of each type.

# BASh v1.5.4

*released 20010212*

## Changes:

Added methods to the ARR module:

ARR\_Set\_Sizes

Added methods to the BLOB module:

BLOB\_BLOB\_to\_Document  
BLOB\_Document\_to\_BLOB  
BLOB\_Find\_Between\_Folding\_x  
BLOB\_Find\_Between\_x  
BLOB\_Find\_Text\_NonCase  
BLOB\_Finds\_Between\_Folding\_x

Added methods to the CODEC module:

CODEC\_Encode\_MD5\_x  
CODEC\_Encode\_MD5\_z  
CODEC\_ERROR

Added the DATE module to the BASh component. Added methods to the DATE module:

DATE\_Get\_RFC\_GMT  
DATE\_Make\_from\_Values

Added methods to the DTS module:

DTS\_Add\_Normalize  
DTS\_Subtract  
DTS\_Subtract\_Normalize

Added methods to the ENV module:

ENV\_ERROR

Added the INIT module to the BASh component. Added methods to the INIT module:

## INIT\_BASh

Added the PROS module to the BASh component. Added methods to the PROS module:

PROS\_Delay\_Current  
PROS\_Get\_Type  
PROS\_Get\_UniqueID

Added methods to the SEM module:

SEM\_ERROR  
SEM\_Test\_One

Added the WORD module to the BASh component. Added methods to the WORD module:

WORD\_Add\_Unsigned  
WORD\_Rotate\_Left

Made the 4D Pack plugin a requirement to use the BASh component; this is not enforced in the code, though.

Fixed a bug in the method *SEM\_Set\_One* in which the determination of whether the method actually set a semaphore which was previously set in the same process was not returning the correct result.

Fixed a bug in the initialization of the RES module in which previously initializing the ENV module would make the RES module think that it too had been initialized.

Fixed bugs in the *SEM\_Set\_One* method wherein the wrong result was returned if the semaphore being set was already set in the current process.

Fixed a bug in *SEM\_Set\_One* in which the delay between check ticks being non-zero could result in an infinite loop waiting for the semaphore, as the timeout checking was reversed incorrectly.

Rebuilt the initialization routines for the ENV module.

Rebuilt the initialization routines for the CODEC module.

Rebuilt the initialization routines for the DSS module.

Changed the way the DSS stack was locked and unlocked in nested calls within the same process.

Rebuilt the initialization routines for the NULL module.

Rebuilt the initialization routines for the RES module.

Fixed a bug wherein kernel processes were not delaying.

Fixed a bug in the method *CODEC\_Decode\_URL\_x* in which an encoded plus byte "+" would be decoded to a space if the "plus to space" option was selected.

# BASh v1.5.3

*released 20001204*

## Changes:

Fixed a bug in the method

***FILE\_Convert\_to\_ResFork\_Windows*** in which the resource fork of a 4D data file was not calculated correctly.

Created the Affix BASh document for handling all resources and data structures essential to the BASh components functionality. Added support for the Affix BASh document throughout the BASh component. Including full long hard file name checking for the Affix BASh document, to be located in the 4DX directory, across all relevant BASh component methods.

Moved all needed resources (only one so far) within the BASh component to instead be distributed in the Affix BASh document, meant to be placed in the 4DX folder. This will facilitate distribution of custom resource types and resources which are not supported directly within components by 4D.

Modified the method ***CODEC\_Encode\_URL\_x*** to instead pull its needed resource from the Affix BASh file instead of from the resource fork of the structure.

Updated the documentation for the method ***CODEC\_Encode\_URL\_x***. The details for the storage location of the "Allowable ASCII Values for URLs" resource changed from the structure document to the new Affix BASh document.

Added another index entry into the Affix BASh document for URL encoded within the CODEC module. This value was for the number 4 (value 52) which was previously missing in the "Allowable ASCII Values for URLs" resource.

Added documentation for Hard File Names within the FILE module. This includes details on what hard file names are, the differences between long and short hard file names, and the storage location for hard file names. This new section is entitled **Hard File Names**.

Updated the installation and updating instructions to account for the Affix BASH document. This section of the developer's manual now includes a section describing in details the Affix BASH document. This new section is entitled **Affix BASH Document**.

Added the BLOB module to the BASH component. This included the following methods:

- BLOB\_Append\_Text
- BLOB\_Clear

Added methods to the ENV module:

- ENV\_Get\_4DXOS\_FolderPath
- ENV\_Get\_4DX\_FolderPath
- ENV\_Get\_BASH\_HardName\_Long
- ENV\_Get\_BASH\_HardName\_Short
- ENV\_Get\_BASH\_RF\_FullPath
- ENV\_Get\_DataFile\_FolderPath
- ENV\_Get\_DirectorySymbol\_by\_OS
- ENV\_Get\_Structure\_DF\_FullPath
- ENV\_Get\_Structure\_FolderPath
- ENV\_q\_Macintosh
- ENV\_Set\_FlushKey

Added methods to the FILE module:

- FILE\_Create\_Document
- FILE\_Create\_Folder
- FILE\_ERROR
- FILE\_Find\_FileName\_Hard\_Long
- FILE\_Find\_FileName\_Hard\_Short
- FILE\_Get\_Document\_List
- FILE\_Get\_Path\_Parent
- FILE\_qi\_Document\_Exists
- FILE\_qi\_Folder\_Exists

Added method to the RES module:

- RES\_Open\_BASH

Added method to the STR module:

STR\_Clean\_EmailUsername

# BASh v1.5.1

*released 20001127*

## Changes:

Added documentation for CLE encoding within the CODEC module. This new section is entitled **CLE Encoding Scheme**.

Added documentation for CONV value types which are not standard 4th Dimension data types. This includes Hex2, Hex8, Type, and Dotted IP values. These new section are entitled **Hex2 and Hex8 Values, Type Values, Dotted IP Values**.

Updated documentation within DSS module to explain the difference between unary and array variable classifications within 4th Dimension. Also, included explanation of mapping table for 4D data type and DSS variable types. This section was entitled **Variable Classifications**.

Added documentation sections within the RES module for the custom resource types. These documentation sections were left for future completion once the functionality for these custom resource types has been integrated into BASh and other DSTi components. These documentation sections are entitled **'fMap' Resource, 'LoCK' Resource, 'MENV' Resource, 'WAGr' Resource, 'WPGGr' Resource**.

Updated documentation within TYPE module to explain the difference between unary and array variable classifications within 4th Dimension. This section was entitled **Unary and Array Classifications**.

Added methods to the ARR module:

```
ARR_Convert_Text_to_Longint  
ARR_Convert_Type_to_Longint  
ARR_Pack_to_Text
```

Added the CODEC module to the BASh component. This included the following methods:

```
CODEC_Decode_Base64_x
```



```
CODEC_Decompose_Base64_z  
CODEC_Decompose_CLE_x  
CODEC_Decompose_URL_x  
CODEC_Encode_Base64_x  
CODEC_Encode_Base64_z  
CODEC_Encode_CLE_x  
CODEC_Encode_URL_x
```

Added the CONV module to the BASH component. This included the following methods:

```
CONV_ASCII_to_Hex2  
CONV_ASCII_to_PrintableText  
CONV_Coerce_from_Text  
CONV_Coerce_to_Text  
CONV_ERROR  
CONV_Hex8_to_Longint  
CONV_Hex8_to_Text  
CONV_IP_to_Longint  
CONV_Longint_to_Hex8  
CONV_Longint_to_IP  
CONV_Longint_to_Type  
CONV_Text_to_Hex8  
CONV_Text_to_Longint  
CONV_Text_to_Real  
CONV_Type_to_Longint
```

Added methods to the DSS module:

```
DSS_Get_Array_by_Unary_Type  
DSS_Get_Unary_by_Array_Type
```

Added the ENV module to the BASH component. This included the following methods:

```
ENV_Get_4DApplication_FullPath  
ENV_Get_Application_Name  
ENV_Get_Application_Name_Short  
ENV_Get_Application_Type  
ENV_Get_DataFile_FullPath  
ENV_Get_DirectorySymbol  
ENV_Get_Platform  
ENV_Get_Structure_RF_FileName
```

ENV\_Get\_Structure\_RF\_FullPath  
ENV\_q\_Windows

Added the FILE module to the BASH component. This included the following methods:

FILE\_Convert\_to\_ResFork\_Windows  
FILE\_FullPath\_to\_FileName

Added the NVP module to the BASH component. This included the following methods:

NVP\_ERROR  
NVP\_Extract\_Values\_by\_Name\_s  
NVP\_Extract\_Values\_by\_Name\_x  
NVP\_Pack\_to\_Text  
NVP\_Parse\_to\_Arrays

Added the RES module to the BASH component. This included the following methods:

RES\_Close  
RES\_Create\_File  
RES\_Delete\_Resource  
RES\_ERROR  
RES\_Get\_Resource\_List  
RES\_Get\_TEXT\_Resource  
RES\_Load\_cicn  
RES\_Load\_fMap  
RES\_Load\_Loack\_LoCK  
RES\_Load\_MBAR  
RES\_Load\_MENU  
RES\_Load\_MENV  
RES\_Load\_PICT  
RES\_Load\_TMPL  
RES\_Load\_WAGr  
RES\_Load\_WPGr  
RES\_Make\_TMPL\_f\_Arrays  
RES\_Open  
RES\_Open\_4DApplication  
RES\_Open\_DateFile  
RES\_Open\_Structure  
RES\_Parse\_TMPL

RES\_Set\_Resource\_Name  
RES\_Set\_Resource\_Properties  
RES\_Set\_TEXT\_Resource

Added the STR module to the BASH component. This included the following methods:

STR\_Clean\_EmailAddress  
STR\_Concatenate\_Text  
STR\_Count\_Occurrences\_of\_ASCII  
STR\_Count\_Occurrences\_of\_String  
STR\_Get\_CharPosition\_by\_ASCII  
STR\_Get\_Line\_First  
STR\_Pad\_String  
STR\_Parse\_to\_Array\_by\_ASCII  
STR\_Parse\_to\_Array\_by\_Str  
STR\_qi\_Match\_Filter\_NonCase  
STR\_Remove\_After\_Last\_by\_ASCII  
STR\_Remove\_Line\_First  
STR\_Remove\_NonAlphaNumeric  
STR\_Remove\_Spaces\_Post  
STR\_Remove\_Spaces\_Pre  
STR\_Remove\_Spaces\_PrePost  
STR\_Replace\_ASCII\_All  
STR\_Wrap\_in\_DoubleQuotes

Added methods to the TYPE module:

TYPE\_Get\_Array\_by\_Unary  
TYPE\_Get\_Unary\_by\_Array

# BASh v1.4.7

*released 20001029*

## Changes:

Added the TIME module to the BASh component. This included the following methods:

- TIME\_Add\_Normalize
- TIME\_Get\_Hours
- TIME\_Get\_Minutes
- TIME\_Get\_Seconds
- TIME\_Get\_Sum\_Offset

Added the DTS modules to the BASh component. This included the following methods:

- DTS\_Add
- DTS\_Get\_Current
- DTS\_Get\_Date
- DTS\_Get\_Date\_Time
- DTS\_Get\_Day
- DTS\_Get\_Maximum
- DTS\_Get\_Month
- DTS\_Get\_Range
- DTS\_Get\_Time
- DTS\_Get\_Year
- DTS\_Make\_from\_DateTime
- DTS\_Make\_from\_Values

Added the method NULL\_Get\_DTS to the NULL module.

Fixed a bug in the DSS module wherein the getting and returning of variables was not indexed correctly. This was introduced with v1.4.6 when the indexing went from 2 digits to 3 digits to support the increased number of variables of each type.

# BASh v1.4.6

*released 20001025*

## Changes:

Expanded the number of supported variables of each type within the DSS module from 50 to 100.

Provided a mapping mechanism within the DSS module to handle string and alpha variable types as text and string array variable types as text arrays.

Completed the documentation of all of the protected and public methods which are available within the BASh component.

# BASh v1.4.1

*released 20001001*

## Changes:

Included limited PDF documentation for the BASh component.

Added some functionality to the SEM module, particularly for greater control in the ***SEM\_Set\_One*** method.

Fixed a bug in the initialization of the different modules. The inclusion of auto-initialization within v1.4.0 caused a small bug which could lead to duplicate initialization calls being made concurrently. This is now fixed in v1.4.1.

## BASh v1.4.0

*released 20000905*

BASh v1.4.0 was released mainly for inclusion on the 4D Summit 2000 CD. It accompanied the notes and materials for two (2) different classes: *If Memory Serves Me Right...* and *Styles Vary*. Notes for both of these classes are available on the Deep Sky Technologies, Inc., web site (<http://www.deepskytech.com/>) and the 4D Zine web site (<http://www.4dzine.com/>).

## BASh pre-v1.4.0

*never released publicly*

Prior to version 1.4.0 of the BASh component, the code which comprised the BASh component was used internally at Deep Sky Technologies, Inc., in all of our projects. It forms the basis for much of the code work and application development which is done at DSTi in 4th Dimension. The code which is in the BASh component has been in use in one form or another at DSTi for at least four (4) years, since the beginning of 1997.

Over the years, the DSS module, contained in the BASh component, has become the single most used module of code within DSTi. No other module of code has been as useful or widely used in all of the projects done at DSTi. The functionality it provides makes variable management and variable reuse simpler than anything else currently available for use when developing in 4th Dimension.





# BASh Error Codes

Coming soon...